

Zetafax 2012 API Help



Fax software solutions for business © 2012 Equisys plc

Zetafax 2012 API Help

© 2012 Equisys plc

All rights reserved. No parts of this work may be reproduced in any form or by any means - graphic, electronic, or mechanical, including photocopying, recording, taping, or information storage and retrieval systems - without the written permission of the publisher.

Products that are referred to in this document may be either trademarks and/or registered trademarks of the respective owners. The publisher and the author make no claim to these trademarks.

While every precaution has been taken in the preparation of this document, the publisher and the author assume no responsibility for errors or omissions, or for damages resulting from the use of information contained in this document or from the use of programs and source code that may accompany it. In no event shall the publisher and the author be liable for any loss of profit or any other commercial damage caused or alleged to have been caused directly or indirectly by this document.

Printed: 2012

Table of Contents

Getting Started	10
Installing the API	
-	
API configuration	
How_to_Develop_and_distribute	17
Support	20
FAQ	21
COM API	23
Overview	
Errors	
	-
Type Libraries	
ZfLib	•
COM Classes	
APIPrint	
A PIPrint.FileName A PIPrint.IsComplete	-
APPrint.Scomplete	
Attachment	
Attachment.Delete	
Attachment.Name	
Attachments	
Attachments.Add	
Attachments.Count	
Attachments.ltem	
Coversheet	
CoverSheet.Name	
Coversheets	
Coversheets.Count	
Coversheets.ltem	
Device	
Device.CurrentPage	
Device.MessageBody	
Device.Name	
Device.NumConnectFails	
Device.NumPages	
Device.NumSendFails	
Device.NumSendOK	
Device.User	
Devices Devices.Count	
Devices.Count Devices.Item	

File	48
File.Delete	49
File.FileName	49
Files	49
Files.Add	50
Files.Count	50
Files.ltem	
Inbox	
Inbox.CheckNew MsgStatus	
Inbox.GetMsg	
Inbox.GetMsgList	
Letterhead	
Letterhead.Name	
Letterheads	
Letterheads.count	
Letterheads.count	
Link	
Link ConnectionOK	
Link.ConnectionOrk	
Link LocalStatus	
Link.NumAcknow ledged	
Link.NumReceived	
Link.NumRejected	
Link.NumRemoteServerError	
Link.NumSentOK	
Link.NumTimedOut	
Link.NumUnAcknow ledged	
Link.RemoteServer	
Link.RemoteStatus	
Links	
Links.Count	
Links.Item	
Message	62
Message.AbortMsg	
Message.DeleteMsg	
Message.GetMsgHistories	63
Message.GetMsglnfo	64
Message.HoldMsg	64
Message.MarkMsgAsRead	64
Message.ReleaseMsg	64
Message.RushMsg	65
Message.SendMsg	65
MessageHistories	65
MessageHistories.Count	66
MessageHistories.ltem	
MessageHistory	
MessageHistory.AddrNum	67
MessageHistory.Connection	
MessageHistory.Date	
MessageHistory.Device	
MessageHistory.ErrorCode	
Messageriistory.Event	
MessageHistory.Name	

Contents

MessageHistory.Organisation	
MessageHistory.PagesSent	
MessageHistory.RemoteServer	
MessageHistory.Route	
MessageHistory.RouteParams	
MessageInfo	
MessageInfo.Attachments	
MessageInfo.Body	
MessageInfo.Comment	
MessageInfo.CoverText	
MessageInfo.CustomField	
MessageInfo.Files	74
MessageInfo.ImageFilePath	
MessageInfo.ImageSize	
MessageInfo.ImageStream	
MessageInfo.Organisation	
MessageInfo.Status	
MessageInfo.Subject	
MessageInfo.Type	
MessageInfo.UserStatus	77
Messages	
Messages.Count	
Messages.ltem	
Messages.MsgDir	
New Message	
New Message.After	
New Message. Attachments	
New Message.Body	
New Message.Charge	
New Message.Comment	
New Message.CoverSheet	
New Message.Covertext	
New Message.CustomField	
New Message.Delete	
New Message.Files	
New Message.Format	
New Message.From	
New Message.Header	
New Message.Hold	
New Message.Letterhead	
New Message.Preview	
New Message.Priority	
New Message.Quality	
New Message.Recipients	
New Message.Send	
New Message.SendTime	
New Message.Subject	
New Message.Text	
New Message.User	
Outbox	
Outbox.CheckNew MsgStatus	
Outbox.GetMsg	
Outbox.GetMsgList	
Recipient	93

	Recipient.Delete	94	4
	Recipient.Fax	. 94	4
	Recipient.Organisation	9	5
	Recipient.To	9!	5
	Recipient.Type	96	6
Rec	cipients		
	Recipients.AddFaxRecipient		
	Recipients.AddLANRecipient		
	Recipients.AddSMSRecipient		
	Recipients.Count		
	Recipients.ltem		
Ser	•		
	Server.Check		
	Server.GetServerInfo		
	Server.Restart		
	Server.Start		
	Server.Stop		
Sor	verlnfo		
OCI	ServerInfo.Coversheets		
	ServerInfo.Deferred		
	ServerInfo.Devices		
	ServerInfo.Letterheads		
	ServerInfo.Links		
	ServerInfo.MaxDevices		
	ServerInfo.MaxLinks		
	ServerInfo.RemoteAccept		
	ServerInfo.RouterSub		
	ServerInfo.Scanning		
	ServerInfo.Sending		
	ServerInfo.WaitingConvert		
	ServerInfo.WaitingDevice		
	ServerInfo.WaitingResend		
Use	erSession		
	UserSession.A PIPrint		
	UserSession.Coversheet	108	8
	UserSession.CreateNew Msg	109	9
	UserSession.FromName		9
	UserSession.Inbox	109	9
	UserSession.Logoff	11(0
	UserSession.Outbox		
	UserSession.SendSubmitFile	11(0
	UserSession.Server	11	1
	UserSession.SystemArea	11	1
	UserSession.UserArea	11	1
	UserSession.UserInDir	11:	2
	UserSession.UserOutDir	112	2
ZfA	PI	112	2
	ZfAPI.GetZetafaxServerInfoFromAD	11:	3
	ZfAPI.GetZetafaxServersFromAD		
	ZfAPI.Logon		
	ZfAPI.LogonAnonymous		
	ZfAPI.RequestDir		
	ZfAPI.ServerDir		
	ZfAPI.SetZetafaxDirs		

Contents

7

ZfAPI.SetZetafaxServerFromAD	116
ZfAPI.SystemDir	117
ZfAPI.UsersDir	117
ZfAPI.Version	118
ZfAPI.ZetafaxServer	118
Type Definitions	118
DevStatusEnum	121
EventEnum	122
FaxTypeEnum	123
FormatEnum	123
HeaderEnum	124
LinkStatus Enum	125
PriorityEnum	
Quality Enum	126
RouteEnum	126
SendTimeEnum	127
Status Enum	127
UserStatusEnum	129
ZfErr	129
Change History	133

C language API

Older API versions	
Function Overview	140
Message information	
Message transmission history	
-	
Message defaults	
Server and device status	150
Function error returns and reference	155
Alphabetical reference	
user_error	
ZfxAbortMsg	
ZfxAPIClosedown	
ZfxAPIInit	
ZfxCheckNewMsgStatus	
ZfxCheckServer	
ZfxCreateAutoFile	
ZfxCreateCtIFile	
ZfxCreateCtlFileEx	
ZfxCreateCtlFileFP	
ZfxCreateDataFile	•
ZfxCreateDataFileFP	
ZfxDeleteMsg	
ZfxGetAPIVersion	
ZfxGetMsgDefaultsEx	
ZfxGetMsgHistory	
ZfxGetMsgHistoryEx	
ZfxGetMsgInfo	
ZfxGetMsgInfoEx ZfxGetMsgList	
ZfxGetMsgList	

ZfxGetSe	erverStatus	198	
ZfxGetSe	ZfxGetServerStatusEx		
ZfxGetSy	ystemArea	202	
ZfxGetU	serArea	203	
ZfxGetU	serCoversheet	204	
ZfxGetUs	serFromname	206	
ZfxGetUs	serInDir	208	
ZfxHold	/lsg	209	
	MsgAsRead		
ZfxRelea	iseMsg	211	
ZfxResta	artServer	212	
	Msg		
ZfxSend	Msg	215	
ZfxSend	MsgEx	217	
	SubmitFile		
ZfxSend	SubmitFileFP	221	
	Server		
	Server		
ZfxVBSe	ndSubmitFile	225	
Dumonial		007	
Dynamic	Data Exchange	227	
Example D	DE Macros	229	
		LLU	
Embedde	d Addressing	231	
	-		
Embedded	Addressing Information	232	
Commands		233	
То		23/	
Name		-	
Fax			
	ation		
Send			
From			
	eet	-	
-			
	ad		
•			
Time		-	
		-	
Attach			
0			
•			
Note		-	
Delete		-	
Using Embe	dded Addressing with Mail Merge	253	
ZSUBMIT		255	
Croating El	IBMIT files	256	
•	נווום ווופס	230	
SUBMIT file	message option lines	258	

	tach	• •	
Ch	narge	. 261	
Co	omment	. 262	
	oversheet		
Co	overtext	• .	
	lete		
Fo	rmat		
	om		
	eader		
Но			
	tterhead		
	eview		
	iority		
	Jality		
	ıbject		
	ser name	-	
SUBMI	T file Message Addressing lines	276	
Fa	х	. 277	
SN	۸S	. 278	
Fie	əld	. 279	
Us	er name	. 280	
Or	ganisation	. 281	
То)	. 282	
SUBMI	T file Message Text commands	283	
An	opend	. 284	
Bo	•		
Da			
Do	wn	. 287	
Fie	eld name	. 288	
Fo	nt	. 289	
Ins	sert	. 290	
La	Indscape	. 291	
Le	۰ ft margin	. 292	
Pa	uge	. 293	
	ortrait	. 294	
Rig	ght	. 295	
Tir	- me		
Un	nderline	. 297	
Action	commands	298	
	end		
	eview		
	ble SUBMIT files		
-			
	ng SMS messages		
-	ble SMS SUBMIT files		
	tting SUBMIT files		
Sending ASCII text files as messages			

The API - Getting Started

Introduction to the API

Without the API

The normal method of submitting messages using Zetafax is to use the client program to manually specify the recipients and message settings. When sending a fax, when a file is printed to the Zetafax printer, or a file is selected for sending from within the client program, the addressing screens are automatically displayed and filled in by the user.

equisys

ΕΤΑ/ΑΧ

Using the API

Using the Zetafax API, there are five additional ways of submitting message to the Zetafax server. These additional methods have been designed to the automatic sending of messages from other applications not only feasible, but extremely easy to implement.

SMS meassages as well as fax messages can be submitted to the Zetafax server with the Zetafax API. The ZSUBMIT program makes it simple to send SMS messages directly from other applications to mobile phones.

Submit files

The simplest method of sending messages is to create an ASCII file in a directory on a fileserver - a "SUBMIT" file. This file can contain both the contents of the message and the addressing information, or these may be broken into two files. Zetafax scans the directory for new files and automatically handles any files it finds, sending messages to either a fax addressee or mobile phone via SMS. A machine with the Zetafax client software installed can be used to monitor the process and resubmit any faxes that fail repeatedly.

Details on how to create SUBMIT files are given in Creating SUBMIT files.

Embedded addressing

Addressing instructions can be embedded into documents created by word processors and other applications to indicate where a fax should be sent, together with a wide range of settings such as the time of sending, priority, resolution, coversheet, and letterhead to use. The commands are embedded in the document using a special syntax; for example:

%%[Fax:123 456 7890]

When the document is printed using the Zetafax printer driver, the embedded addressing commands are used by the Zetafax client program in place of the addressing dialogs. Provided adequate details are given using embedded commands, no dialogs will be displayed and the fax or faxes will be submitted to the Zetafax server automatically.

When sending faxes automatically from other Windows applications, it may be simplest to embed the addressing information in the message itself using embedded commands, prior to printing it using the Zetafax Windows printer driver. This is supported as one of the API toolkit alternatives.

DDE commands

Dynamic Data Exchange (DDE) may be used to pass addressing information across from a Windows application to the Zetafax client, prior to printing a message using the Zetafax Windows printer driver.

COM and C Language libraries

The most powerful way of passing faxes across to the Zetafax server for sending is using the COM or C language API. This allows for the monitoring of the status of a queued message, including the retrieval of a full history log once a message has completed.



Installing the API

The Zetafax API offers five methods of automatically submitting messages to the Zetafax server, the automatic submission program, embedded addressing, DDE and the COM and C language libraries which are all independent. This section explains how each feature is installed on your system. You should refer to the appropriate section once you have decided which method you intend to use.

Licensing of the API depends on which API product you have purchased. For users of Zetafax network fax software, please refer to the section entitled "Zetafax API Toolkit", and for Equisys (Independent Software Vendor) ISV partners, please refer to section entitled "Zetafax engine".

Zetafax API Toolkit

If Zetafax is currently up and running on your network, then the automatic submission, embedded addressing and DDE features of the Zetafax API are already installed! You only need to activate these features by adding the API toolkit license number in the modify license details dialog in the **Zetafax Configuration** program.



Fax engine

If Zetafax has been supplied to you as an Equisys (Independent Software Vendor) ISV partner, there is no need to add a separate API license as described above. The Zetafax fax engine products supplied to ISV partners include the API license as standard within the starter system license number.

ZSUBMIT

The ZSUBMIT program is distributed with the Zetafax server programs, and is stored in the same directory as the other programs (zfax \SERVER by default, where zfax is the server base directory specified when Zetafax was installed).

Embedded addressing

Embedded addressing requires the Zetafax printer driver to be installed on all of the Zetafax clients wishing to use this feature. The Zetafax printer driver is installed by running the Workstation Setup program (WKSETUP) - refer to the Installation and Configuration Guide for detailed instructions on using this program. There is limited support for embedded addressing available without the API, and the full functionality is provided when the API toolkit has been purchased.

DDE

Support for Dynamic Data Exchange (DDE) is built in to the Zetafax client software. As for embedded addressing, there is limited support for DDE in the standard Zetafax software. Full support is available only when the API toolkit has been purchased.

C language API

The C language libraries and 32-bit dynamic link library are provided separately in a self-extracting executable. The appropriate libraries need to be copied into your development environment and if used,

Zetafax 2012 API Help

the DLL needs to be copied to the relevant location. Please refer to $\underline{C \text{ language API}}$ for more detailed information.

Programs written using the Zetafax C language API may only be run on Zetafax systems with an API license.

COM API

Like all COM components ZfAPI32.dll must be registered before it can be used. This is done using the program regsvr32 as follows:

1. Ensure the program regsvr32 is present in the same location as the ZFAPI32.dll file.



2. In a DOS window, set to this directory, use the following command to run the registration program: Run %system32%\regsvr32 ZfAPI32.dll.

3. A dialog box should appear confirming that the registration was successful.



Note: If you have installed the Zetafax client onto your development computer, the COM API is installed and registered automatically. It is installed by default to C:\Program Files\Common Files\Equisys.

🕽 Back 👻 🕥 🗸 🏠	Tools Help		1 2
ddress 🛅 C:\Program Files\C	ommon Files\Equisys		• • 60
2fapi32.dll 9.0.324.0	9.0.	nlib.dll 324.0	
ZFAPI32	Zeta	afax-GoldMine Integra	ation
ActiveX Control			



API configuration

From the Zetafax Configuration program, located on the Zetafax server, you can adjust the parameters specific to the ZSUBMIT program. Select the ZSUBMIT automatic file submission program option from the Server settings options:



Selecting this option will open the Zetafax - configuration options dialogue:

Zetafax - configura	ation options	×
Category	ZSUBMIT automatic file submission program The ZSUBMIT program is part of the optional Zetafax API. It allows programs to send faxes automatically by creating text files.	OK Cancel
Text files	Directory for files C:\PROGRAM FILES\ZETA Scan frequency 10 secs Zetafax user account	Reset <u>H</u> elp
Queuing	Default user (none) Carl Allow any user Carl Delete successful messages Maximum queued messages allowed Select from the category list on the left for more options	

These options are already setup with values, allowing the ZSUBMIT program to be used however, you can change these settings to better meet your needs:

Directory for files

Specify the directory which the ZSUBMIT program looks in for SUBMIT files to send. Any files found whose names match the given specification (normally "*.SUB" - see Expert setup options will be interpreted as SUBMIT format files and submitted to the server for sending.

Scan frequency

Specify the polling interval, in seconds. This is how often the program looks for SUBMIT files in the directory for sending and check the status of messages already queued. Reducing this value will increase the processing overhead of the program.

Zetafax user account

Set up the user account details for use with auto submission of faxes.

Default user

Specify the Zetafax user account to be used when submitting files. All messages will be sent as if by this user, unless a user name is specified in the SUBMIT file. If the user name is left blank then each SUBMIT file must specify a user name.

Allow any user

Specify whether users can specify the Zetafax user name in the SUBMIT file, overriding the name given in the Default user field. Do not check this box if you want to ensure that messages can only be submitted as the given user when using the ZSUBMIT program (e.g. for permissions or security reasons).

Delete successful messages

Check this box if faxes that have been sent successfully (i.e. faxes that would be displayed on the Zetafax Client with a tick) should be deleted automatically. This is useful in systems where a large number of faxes are being submitted automatically and you just want to check for any which have failed.

Maximum queued messages allowed

Specify the maximum number of messages that may be active in the queue for this user at any one time.

Zetafax 2012 API Help

If the value is 0 then any SUBMIT file found in the directory will be submitted to the server immediately, when it is found. Otherwise the file is only submitted if the number of active messages is less than the specified value. The program will wait for one of the existing messages to complete, before submitting the file.

ΟΚ

Save any changes that have been made to the ZSUBMIT automatic file submission program configuration, and exit the Zetafax - configuration options dialog.

Cancel

Do not save changes made to the ZSUBMIT automatic file submission program configuration, and exit the Zetafax - configuration options dialog.

Reset

Reset the ZSUBMIT automatic file submission program configuration to its default settings. The settings are not saved until either OK is clicked or another category icon is selected from the scroll (left).

If you use the scrolling icons on the left to move to another Category, any changes made to the ZSUBMIT automatic file submission program configuration are saved.

Related topics The ZSUBMIT program



How to Develop and distribute your fax-enabled application

Developing your application

1) Request an Equisys API Developer Kit

The Equisys API Developer Kit is available to all Equisys ISV partners. Included in the kit is a 5 user, 2 lines Zetafax server and the developer tools required to develop fully integrated applications.

Full documentation on how to install the server software and on using the development tools is included in the documentation supplied with the developer kit. Additional resources are available free of charge in the support section of the Equisys web site http://www.equisys.com/

2) Install the Zetafax API and developer tools

The Zetafax API runs under Windows, and supports the same operating systems as the Zetafax server. One or more fax modems, active ISDN controllers or intelligent fax boards are required for sending and receiving faxes. Installation is a very simple process and should take less than 10 minutes.

During the install process, you will be required to enter a license number supplied with the system, which enables both the server and development tools.

You will also need to create a Zetafax user account to use for sending and receiving messages. This can be done during installation or afterwards, using the Zetafax Configuration program. We recommend that you either choose an account name and description like AUTOUSER or APIUSER, or one which is clearly connected with your company or application (e.g. MYCO or MYAPP). Note that you do not need to create a network account unless you require it for enhanced security - the Zetafax account does not need to be linked to a network login, though doing so will allow the Zetafax client to login automatically when started.

The installation steps required for the developer tools depend on the method you intend to use to integrate your application with the API, as follows:

COM API and C language libraries:

The Zetafax API is installed as part of the Zetafax API install to \zfax\ZFAPI. The installed folders contain libraries and include files; you should add the appropriate folders to your development tools (IDE).

API library functions communicate directly with the Zetafax server, using shared files. The API determines the location of the server through the presence of two files - either a file called ZETAFAX.INI, typically stored in the Program Files\Zetafax Server folder, or a file called ZFCLIENT.INI, typically stored either in the Program Files\Zetafax folder or the user's Application Data folder. ZETAFAX.INI is created when the Zetafax Server is installed. ZFCLIENT.INI is generated when the Zetafax client is run for the first time; however the file can sometimes be copied from another computer if preferred. In addition, registry values can be added to help the API locate these files. These registry values are:

Value Name	Registry Location	Description
ZetafaxIniPath	HKEY_LOCAL_MACHINE\Software\Equisys\Zetafax Serve	rString value pointing to
		ZETAFAX.INI file path (e.g. c:\zetafax\server)
ZetafaxClientIniPath	HKEY_LOCAL_MACHINE\Software\Equisys\Zetafax	String value pointing to ZFCLIENT.INI file path (e. g. c:\zetafax\client)

ZSUBMIT:

ZSUBMIT is an automatic submission program which is run automatically as part of the Zetafax server. It scans a single folder for messages to be sent - this is zfax \SERVER\Z-TEMP by default, though the location can be changed in the Zetafax Configuration program.

To use ZSUBMIT from your application there are no specific installation requirements, other than to ensure

that the server is configured to look in the folder your application will use.

Embedded addressing:

Embedded addressing commands are handled by the Zetafax Printer and Zetafax client program. The Zetafax client must be installed on the application computer, and the Zetafax server and Zetafax client must be running before printing to the Zetafax Printer (though the Zetafax Printer will start the client automatically if set to login automatically).

DDE:

DDE commands are handled by the Zetafax client program. The Zetafax client must be installed on the application computer, and the Zetafax server and Zetafax client must be running before initiating a DDE conversation.

3) Register the Zetafax API object model library (if you have not installed the Zetafax client)

If you intend to use the COM API (e.g. from a Visual Basic program), then you will need to register the object model library on the development computer. You do this from a command prompt as follows: Change directory to the location of ZFAPI32.DLLType the command REGSVR32 ZFAPI32.DLL A dialog box should appear confirming that the registration was successful.

Note: If you have installed the Zetafax client onto your development computer, the COM API is installed and registered automatically. It is installed by default to C:\Program Files\Common Files\Equisys.

4) Develop and test your custom application

Develop your application as normal. We recommend that your test cases include a variety of error scenarios such as number busy retries; these will depend on the degree and method of integration used, and the extent to which the application is intended to cope with normal errors unattended.

For test purposes, devices on the Zetafax server can be configured in demonstration mode. In this mode of operation the server simulates sending messages without connecting to the device. This removes the need for external connections and destination devices, and reduces the cost for high volume testing.

You configure a device for demonstration mode by editing the configuration file SETUP.INI (located in *zfax* SYSTEMZ-DB). Find the section for the device towards the end of the file (e.g. [FCLASS-1]), then add the following line at the end of the section:

DemoMode: SLOW SEND

Now restart the Zetafax server, and check that the device controller reports Demonstration mode enabled as it starts.

Deploying your application at a customer site

1) Obtain a Zetafax API product copy

When you are ready to deploy your fax-enabled solution to your customer, you will need to purchase the appropriate API product for your application from Equisys. You should also ensure that your customer has the appropriate hardware i.e. a PC server, fax hardware and telephone lines available prior to installation.

2) Install the Zetafax API

The Zetafax API typically includes a 1 user, 1 line Zetafax server, with special licensing to enable the API options. The API products include a CD-Rom with the software and a license number. Please refer to the documentation supplied in your developer kit or on the API CD-ROM for installation instructions. During installation, the Zetafax server software will be automatically registered with Equisys.

Create a Zetafax user account to use for sending messages, using the Zetafax Configuration program. This will typically have the same account name used when developing the application (see above), since applications written using the COM API, C language libraries or ZSUBMIT may specify the user name when they run.

Test that the API is correctly configured by sending and receiving a fax using the client software. Instructions are supplied in the Software Guide supplied with your Developer Kit or on the CD-ROM.

3) Install your custom application, including redistributable Zetafax API components

After installing your application you may need to carry out additional steps, depending on the method your application uses to integrate with the API, as follows:

COM API and C language libraries:

Install the Zetafax client program (*zfax* \SYSTEM\WKSETUP.EXE), this will create a ZFCLIENT.INI file and also install the ZFAPI32.DLL.

Or

Alternatively, you can create the ZFCLIENT.INI file by copying it from another computer if preferred and copy the following redistributable file from the API Developer kit:

File ZFAPI32.DLL, to be copied to %windir%\SYSTEM32

ZSUBMIT:

There are no specific installation requirements, other than to ensure that the server is configured to look in the folder your application will use.

Embedded addressing:

If your custom application is not running on the Zetafax server computer, install the Zetafax client by running the Zetafax Workstation Setup program ($zfax \SYSTEM WKSETUP.EXE$).

DDE:

If your custom application is not running on the Zetafax server computer, install the Zetafax client by running the Zetafax Workstation Setup program (*zfax* \SYSTEM\WKSETUP.EXE). You may also wish to set the Zetafax client to startup automatically, by copying it to the Startup program group.

4) Register the ZFAPI.DLL (if you are using COM API and have not installed the Zetafax client)

If your custom application uses the COM API (e.g. from a Visual Basic program), then you will need to register the object model library on the server on which your custom application is installed. You can do this manually from a command prompt as follows:

Change directory to the location of ZFAPI32.DLL (i.e. %windir%\SYSTEM32)Type the command REGSVR32 ZFAPI32.DLL A dialog box should appear confirming that the registration was successful.

Alternatively you can do this automatically by calling REGSVR32 from your install program.

Note: If you have installed the Zetafax client, the COM API is installed and registered automatically. It is installed by default to C:\Program Files\Common Files\Equisys.



Contact and Support

If you require assistance with using or operating the software, please follow this procedure:

- 1. Read the on-line help manuals.
- 2. Search the support pages, and especially the technical notes section, on the Equisys web site at: http://www.equisys.com/support
- 3. Contact the software supplier from whom you purchased the software. In most cases the supplier will be able to provide support.

Please note that support is only available in selected countries, and you should contact your distributor for availability.

Please feel free to contact Equisys (or any of our distributors) with any comments or suggestions you may have about the software or the manual.

Equisys plc

http://www.equisys.com

Sales

Tel (020) 7203 4001 Fax (020) 7203 4005 sales@equisys.com

Technical support

Tel (020) 7203 4002 Fax (020) 7203 4005 <u>support@equisys.com</u>

Equisys Inc (USA and Canada)

Sales Tel (770) 772 7201 Fax (770) 442 5789 sales@zetafax.com

Technical support Tel(678) 942 7250 Fax(770) 442 5789 support@zetafax.com



Frequently Asked Questions

Q: What is the difference between the COM API and the C API?

A: The COM API is a wrapper for the C API. It adds a hierarchical structure to the function calls, and represents the API's complex structures as collections of objects. It was written to make the API more accessible from people writing applications with scripting languages and Visual Basic.

Q: Can you show me some code?

A: Using the COM API from within Visual Basic to send a high priority fax in 9 lines:

' Declare objects

Dim oZfAPI As New ZfLib.ZfAPI Dim oUserSession As ZfLib.UserSession Dim oNewMessage As ZfLib.NewMessage

' Logon and create new message:

Set oUserSession = oZfAPI.Logon("JJONES", False)
Set oNewMessage = oUserSession.CreateNewMsg

' Set properties:

oNewMessage.Recipients.AddFaxRecipient "Sam Smith", _"ACME plc", "020 7123 4567" oNewMessage.Text = "I am a fax!" oNewMessage.Priority = zfPriorityUrgent

' Send!

oNewMessage.Send

Q: What can you do with the COM API?

A: You can use the API to send faxes and to enumerate sent and received faxes. It can also be used to stop and start and gather status information about the Zetafax server, its devices and its LCR links.

Q: What can you not do with the COM API?

A: You cannot use the COM API to add, edit or delete users, or change the Zetafax server's configuration.

Q: With which development environments can the COM API be used?

A: It is compatible with all development environments which support COM, e.g. Visual Basic 6, Visual C++ 5 and 6, and Visual Studio .NET.

Q: Can you use the COM API with ASP?

A: Yes, but if the Zetafax server is installed on another computer you need to make sure that the web site is running as a user with permissions to access network drives, not the IWAM, IUSR or ASPNET accounts. (On Windows 2000 this could be done with COM+).

Q: In what language is the COM API written?

A: The API is written in C, the COM API is written in C++.

Q: With which operating systems is the COM API compliant?

A: The COM API is supported on all operating systems supported by the Zetafax client. (95, 98, Me, NT4, W2K, W2K3 and XP).

Q: Does the COM API work with managed code?

A: Yes. Once the COM API is registered you need to import it as a reference.

Q: Is the API thread-safe?

22

A: No. If you are using the API in a multi-threaded application it is best to protect all access to the Zetafax API with a critical section.

Q: How do you secure the COM API?

A: Zetafax stores user's files on the file system. To secure Zetafax you use NT security to only allow certain people access to each user's files.

Q: How does the COM API handle authentication?

A: You have to log on as a Zetafax user to user the COM API. To stop someone logging on to another user's account you have to use NT security on your file system.

Q: Which file formats are supported by the COM API?

A: By default, the API only supports text, G3N, G3F and some standard graphics formats. (Such as GIFs or Bitmaps). However, if you have the document rendering add-on, Doctiff, you can use over 200 other file types as well (see <u>ZTN1261 - INFO File types supported by document conversion add on DOCTIFF</u>).

Q: Can the COM API handle files as streams?

A: No, the API assumes that all files are already stored on the file system.

Q: Does the COM API support events?

A: No, you have to poll for changes.

Q: Can I use the COM API to send SMS messages?

A: Yes, however in the current version of the COM API the method is marked as hidden in the type library.

See ZTN1239 - HOWTO Develop and redistribute your fax-enabled application for details.

References

ZTN1239 - HOWTO Develop and redistribute your fax-enabled application ZTN1261 - INFO File types supported by document conversion add on DOCTIFF



COM API

This help provides assistance on the COM API and the Zetafax Object Model.

For a brief introduction please read the **Overview**.

The details of the individual objects can be found in the \underline{ZfLib} library.



Overview

Introduction

This document tells you how to configure and use the COM API.

Registration

Like all COM components ZfAPI32.dll must be registered before it can be used. This is done using the program regsvr32 as follows:

- 1. Change directory to location of ZfAPI32.dll
- 2. Run %system32%\regsvr32 ZfAPI32.dll
- 3. A dialog box should appear confirming that the registration was successful.

Using the COM API in Visual Basic

The COM API is primarily intended for people using Visual Basic. There are two ways of doing this:

• The recommended way is to add the Zfapi32 type library as a reference to your project. This enables early binding and access to all the constants and interfaces:

```
' Create new Zetafax object and Logon
Dim oZfAPI as New ZfLib.ZfAPI
Dim oUserSession as ZfLib.UserSession
Set oUserSession = oZfAPI.Logon("ADMINIST", False)
```

You can also use the IDispatch interface and create objects using CreateObject and the ProgID:

```
' Create new Zetafax OBJECT USING CreateObject and Logon
DIM oZfAPI AS OBJECT
DIM oUserSession AS OBJECT
Set oZfAPI = CreateObject("ZfAPI32.ZfAPI")
Set oUserSession = oZfAPI.Logon("ADMINIST", FALSE)
```

Using the COM API in Visual C++

There are three ways of accessing COM objects in Visual C++:

- Win32 API. (Only for those who like to do it the hard way!)
- MFC OLE can be used to generate class wrappers for the ZfAPI32 type library using the Class Wizard.
- People using version 5.0 and later of Visual C++ can use the #import compiler directive to import ZfAPI32.dll. The compiler generates header files containing classes wrapping the interfaces, smart pointers, and the typdefs for the enumerations. This is the recommended way to use the COM API in Visual C++.

For example:

```
// Import Zetafax DLL without the ZfLib % \mathcal{A} = \mathcal{A} = \mathcal{A} namespace this will
```

// generate two header files, ZfAPI32.tlh and ZfAPI32.tli,

// which contain the definitions of the interfaces and enums
#import "ZfAPI32.dll" no_namespace

```
void DoSomething()
```

{

```
// Create new Zetafax object and Logon
IZfAPIPtr pZfAPI(_T("ZfAPI32.ZfAPI"));
```

```
IZfUserSessionPtr pUser(pZfAPI->Logon(_T("ADMINIST"), false);
```

Using the COM API in .NET

}

1. From within Visual Studio select the add a reference option. The following menu will appear:

Component Name	TypeLib Ver	Path		Browse
Xceed SmartUI v2.0	1.3	C:\Program Files\Xceed Com	<u>ا</u> ا	Select
Xceed Streaming Compression	1.1	C:\Program Files\Xceed Com		e gerer.
Xceed Winsock Library v1.2	1.2	C:\Program Files\Xceed Com		
Xceed Zip Compression Librar	5.0	C:\Program Files\Xceed Com		
xenroll 1.0 Type Library	1.0	C:\WINDOWS\System32\xen		
zClientM 1.0 Type Library	1.0	C:\Program Files\MSN Gamin		
Zetalink Exchange Agent Clas	1.0	C:\Program Files\Zetalink\Exc		
ZetaSnap 1.0 Type Library	1.0	C:\Program Files\Zetafax Ser		
Zfapi32 1.4 Type Library	1.4	C:\Program Files\Common Fil		
zfGMLib 1.0 Type Library	1.0	C:\Program Files\Common Fil		
ZfViewX ActiveX Control module	1.1	C:\Program Files\Common Fil	-	
]	546043			
ected Components:	Туре	Source		Remo <u>v</u> e
fapi32 1.4 Type Library	COM	C:\Program Files\Common Files\		

2. Select the COM tab option

3. Move to the end of the list, and search for the Zfapi32 1.4 Type library component. Select it by ensuring the component is selected and clicking on the Ok button.

Should the Zfapi32 1.4 Type library component not be present, then select the browse option to search for the *.dll file. In a standard Zetafaxsetup, this file is found in the following location:

C:\Program Files\Zetafax Server\ZFAPI\LIB\I386\Microsoft

4. You can now call functions present in the Zetafax library, by using references to the Zflib namespace within your code for example:

ZfLib.ZAPI

5. Ensure you distribute the interop.zflib.dll file found in the build directory of your code.

Code Samples

The following samples are written in C# and Visual Basic .NET. The other .NET languages (Managed C++, Visual J#) are very similar and these examples can easily be adapted for use in these environments.

Zetafax 2012 API Help 26

Note: To avoid the usage of long type-names declare the following namespace at the top of the file: using ZfLib;

The API fully supports exception handling and it is recommended that you use the try-catch mechanism to receive meaningful error messages and descriptions from the Zetafax COM API . (The examples below demonstrate this).

1. The following example demonstrates sending a fax using the COM API:

VB.NET:

```
' Declare objects
             Dim oZfAPI As New ZfLib.ZfAPI
             Dim oUserSession As ZfLib.UserSession
             Dim oNewMessage As ZfLib.NewMessage
            Try
                 ' Logon and create NewMessage:
                 oUserSession = oZfAPI.Logon("ADMINIST", False)
                 oNewMessage = oUserSession.CreateNewMsg
                 ' Set properties:
                 oNewMessage.Recipients.AddFaxRecipient("Sam Smith", _
                                                        "ACME plc",
                                                         "020 7123 4567")
                 oNewMessage.Text = "I am a fax!"
                 oNewMessage.Priority = ZfLib.PriorityEnum.zfPriorityUrgent
                 ' Send!
                 oNewMessage.Send()
            Catch ex As Exception
                 System.Windows.Forms.MessageBox.Show(ex.Message,
            "ZetaFax Error",
            MessageBoxButtons.OK,
            MessageBoxIcon.Error)
            End Try
C#:
      // Declare objects
      ZfAPIClass oZfAPI = new ZfAPIClass();
      UserSession
                            oUserSession;
      ZfLib.NewMessage oNewMessage;
      trv
       {
             // Logon and create NewMessage:
             oUserSession = oZfAPI.Logon("ADMINIST", false);
             oNewMessage = oUserSession.CreateNewMsg();
             // Set properties:
             oNewMessage.Recipients.AddFaxRecipient("Sam Smith", //TO
                                                          "ACME plc",
                                                                           - 11
Organization
                                                          "020 7123 4567");//Fax number
             oNewMessage.Text = "I am a fax!";
             oNewMessage.Priority = ZfLib.PriorityEnum.zfPriorityUrgent;
```

```
// Send!
             oNewMessage.Send();
      }
      catch (System.Runtime.InteropServices.COMException ex)
       {
             System.Windows.Forms.MessageBox.Show(ex.Message,
"ZetaFax Error", MessageBoxButtons.OK, MessageBoxIcon.Error);
      }
```

2. The code below demonstrates message information handling:

VB.NET:

```
' Declare objects:
     Dim strBody As String
     Dim oZfAPI As New ZfLib.ZfAPI
     Dim oUserSession As ZfLib.UserSession
     Dim oMessage As ZfLib.Message
     Dim oMsgHist As ZfLib.MessageHistory
     Try
          strBody = "~ZAPI001"
          ' Logon and get message:
         oUserSession = oZfAPI.Logon("ADMINIST", False)
         oMessage = oUserSession.Outbox.GetMsg(strBody)
          ' Display information about the message
         With oMessage.GetMsgInfo()
              txtCaption.Text = .Body
              txtSubject.Text = .Subject
              txtComment.Text = .Comment
          End With
          ' Display the number and call duration for each recipient:
         Dim MessageHistoryEnum As IEnumerator
         MessageHistoryEnum = oMessage.GetMsgHistories.GetEnumerator()
         While MessageHistoryEnum.MoveNext
              oMsgHist = MessageHistoryEnum.Current
              lstHistory.Items.Add("To: " & oMsgHist.Name &
                       " Time Taken: " & oMsgHist.Date.ToString())
          End While
     Catch ex As Exception
         System.Windows.Forms.MessageBox.Show(ex.Message,
"ZetaFax Error", MessageBoxButtons.OK, MessageBoxIcon.Error)
     End Try
```

// Declare objects:

```
string strBody;
ZfAPIClass oZfAPI = new ZfAPIClass();
UserSession oUserSession;
ZfLib.Message oMessage;
ZfLib.MessageHistory oMsgHist;
```

C#:

```
try
       {
              strBody = "~ZAPI001";
              // Logon and get message:
              oUserSession = oZfAPI.Logon("ADMINIST", false);
              oMessage = oUserSession.Outbox.GetMsg(strBody);
              // Display information about the message
              txtCaption.Text = oMessage.GetMsgInfo().Body;
              txtSubject.Text = oMessage.GetMsgInfo().Subject;
              txtComment.Text = oMessage.GetMsgInfo().Comment;
              // Display the number and call duration for each recipient:
              string szFormattedHistoryItem;
       IEnumerator MessageHistoryEnum = oMessage.GetMsgHistories().GetEnumerator
();
              while (MessageHistoryEnum.MoveNext())
              {
                     oMsgHist = (ZfLib.MessageHistory) MessageHistoryEnum.
Current;
                     szFormattedHistoryItem = string.Format("To:{0} TimeTaken:
{1}",
                    oMsgHist.Name,
                    oMsgHist.Date.ToString());
                     lstHistory.Items.Add(szFormattedHistoryItem);
              }
       }
       catch (System.Runtime.InteropServices.COMException ex)
       {
              System.Windows.Forms.MessageBox.Show(ex.Message,
"ZetaFax Error", MessageBoxButtons.OK, MessageBoxIcon.Error);
       }
```

3. The following code demonstrates how to retrieve Zetafax device information:

VB.NET:

```
' Declare objects:
Dim oZfAPI As New ZfLib.ZfAPI
Dim oUserSession As ZfLib.UserSession
Dim oDevices As ZfLib.Devices
Dim oDevice As ZfLib.Device
Try
    ' Logon and get devices:
    oUserSession = oZfAPI.Logon("ADMINIST", False)
    oDevices = oUserSession.Server.GetServerInfo().Devices
    ' Enumerate devices adding information to Listbox:
    Dim DeviceEnum As IEnumerator
    DeviceEnum = oDevices.GetEnumerator()
    While DeviceEnum.MoveNext
```

```
'Iterate through the devices
oDevice = DeviceEnum.Current
lstDevices.Items.Add(oDevice.Name & " " & oDevice.User)
End While
Catch ex As Exception
System.Windows.Forms.MessageBox.Show(ex.Message,
"Zetafax Error", MessageBoxButtons.OK,
MessageBoxIcon.Error)
End Try
```

C#:

```
// Declare objects:
ZfAPIClass oZfAPI = new ZfAPIClass();
UserSession
                   oUserSession;
ZfLib.Devices oDevices;
ZfLib.Device oDevice;
try
{
       // Logon and get devices:
      oUserSession = oZfAPI.Logon("ADMINIST", false);
      oDevices = oUserSession.Server.GetServerInfo().Devices;
      // Enumerate devices adding information to Listbox:
      IEnumerator DeviceEnum = oDevices.GetEnumerator();
      while(DeviceEnum.MoveNext())
       {
             oDevice = (ZfLib.Device)DeviceEnum.Current;
             lstDevices.Items.Add(oDevice.Name + " " + oDevice.User);
      }
}
catch (System.Runtime.InteropServices.COMException ex)
{
      System.Windows.Forms.MessageBox.Show(ex.Message,
       "ZetaFax Error",
      MessageBoxButtons.OK,
      MessageBoxIcon.Error);
}
```

The Zetafax Object Model

This diagram shows the various objects in the Zetafax object model, and how they are linked. Normal rectangles represent objects, shaded rectangles represent collections.

The ZfAPI object is the only object that can be created directly. All others can only be accessed by traversing the object tree.



Examples of the use of the COM API

Add the name of each device and the person using it into a list box:

```
' Declare objects:
```

```
Dim oZfAPI As New ZfLib.ZfAPI
Dim oUserSession As ZfLib.UserSession
Dim oDevices As ZfLib.Devices
```

Display information about a specific message:

```
' Declare objects:
Dim strBody As String
Dim oZfAPI As New ZfLib.ZfAPI
Dim oUserSession As ZfLib.UserSession
Dim oMessage As ZfLib .Message
Dim oMsgHist As ZfLib.MessageHistory
strBody = "~ZAPI001"
' Logon and get message:
Set oUserSession = oZfAPI.Logon("ADMINIST", False)
Set oMessage = oUserSession.Outbox.GetMsg(strBody)
' Display information about the message
With oMessage
      msgForm.Caption = .Body
      txtSubject = .Subject
      txtComment = .Comment
End With
' Display the number and call duration for each recipient:
For Each oMsgHist
In oMessage.GetMsgHistories
      lstHistory.AddItem
       "To: " & oMsgHist.AddrNum &
              " Time Taken:"
                               & oMsgHist.Connection
Next
```

Send a fax:

oNewMessage.Send



Error Codes

This document explains what various errors returned by the COM API mean:

			COM error	Error description
E_INVALID_PARAMO	Error 0xF700	Error 62720	0x8004F700	An invalid parameter was passed to the Zetafax
APIE_NOT_INIT C	0xF701	62721	0x8004F701	A call was made to the API when it had not been initialised with a call to ZfAPI. Logon
E_INIT_FAIL C E_INVALID_ZF_INIC T FILE		62722 62723	0x8004F702 0x8004F703	The API failed to initialise The API had problems reading ZETAFAX.INI
E_INVALID_ZF_US (ER)xF704	62724	0x8004F704	An attempt was made to log on to the API with an invalid user
E_CANNOT_LOG_OON	0xF705	62725	0x8004F705	The user was already logged on or the API cannot access their directories
E_PATH_NOT_FOU (0xF706	62726	0x8004F706	The API was passed an invalid path
E_TOO_MANY_FILE(0xF707	62727	0x8004F707	There are too many files in this directory
E_FILE_CREATE_E C	0xF708	62728	0x8004F708	Too many open files
E_FILE_OPEN_ERR (0xF709	62729	0x8004F709	Could not open file
	DxF70A DxF70B	62730 62731	0x8004F70A 0x8004F70B	Could not read/write to file The file could not be found
E_SERVER_NOT_R (DxF70C	62732	0x8004F70C	The Zetafax server isn't running
E_INVALID_DATA_C	0xF70D	62733	0x8004F70D	The data file format specified is not recognised
E_MSG_UNKNOWN (DxF70E	62734	0x8004F70E	The specified message could not be found
E_MSG_NOT_COM (PLETED	DxF70F	62735	0x8004F70F	An attempt was made to modify a message that wasn't completed
E_MSG_EXISTS C E_INFO_FILE_OPENC ERROR	0xF710 0xF711	62736 62737	0x8004F710 0x8004F711	This message already exists Could not open MSGDIR.CTL
E_INFO_FILE_ERR (0xF712	62738	0x8004F712	Error updating/accessing MSGDIR.CTL
E_INFO_FILE_INVA (0xF713	62739	0x8004F713	MSGDIR.CTL is invalid
E_CANNOT_SUBMI (0xF714	62740	0x8004F714	Error handling .SUB file
E_BUFFER_TOO_S (0xF715	62741	0x8004F715	The buffer in which to return data was too small
E_SUBMIT_FILE_INC	0xF716	62742	0x8004F716	One or more lines in the specified .SUB file were invalid
E_CANNOT_READ_C MSG_DEFAULTS	0xF717	62743	0x8004F717	Cannot read user's USER.INI
E_CONTROL_FILE_C	DxF718	62744	0x8004F718	The API was unable to open the message's CTL file
E_CONTROL_FILE_0	0xF719	62745	0x8004F719	Error reading/writing CTL file

ERROR			
E_CONTROL_FILE_0xF71A INVALID	62746	0x8004F71A	CTL file is corrupt
E_SERVER_RUNNI 0xF71B	62747	0x8004F71B	The Zetafax server is running
E_NO_START_SYS 0xF71C MAN	62748	0x8004F71C	The API could not launch SYSMAN.EXE
E_SERVER_INI_FIL 0xF71E E ERROR	62750	0x8004F71E	Problems accessing SETUP.INI
E_FUNCTION_ABO 0xF71F RT	62751	0x8004F71F	The function failed because a user defined callback function returned "Abort and Stop" status
E_TIMEOUT_EXPIR 0xF720 ED	62752	0x8004F720	The specified function did not complete within the timeout period
E_MALLOC_FAILED 0xF724	62756	0x8004F724	The API ran out of memory.
E_LICENCE_ERROR0xF725	62757	0x8004F725	The API Could not find the Zetafax licence
E_API_LICENSE_ER0xF726 ROR	62758	0x8004F726	Your Zetafax licence does not permit you to use the API
E_USER_NOT_INIT 0xF727	62759	0x8004F727	The API couldn't find the user of this session
E ACCESSDENIED 0xF728	62760	0x8004F728	Access Denied
E_FULLCOLLECTIO 0xF730 N	62768	0x8004F730	The collection is full



The second secon

This is a list of the objects and enumerations that appear in the Zetafax COM library $\ensuremath{\textbf{Groups}}$

COM Classes

API Print	This object allows the API to
	print via the Zetafax Printer.
	The <u>Attachment</u> object
Attachment	contains the name of a
	Zetafax attachment to be
	attached to a message before
	it is sent.
-T- - - - - - - - - -	The <u>Attachments</u> collection
Attachments	object contains <u>Attachment</u>
	objects.
	The <u>Coversheet</u> class
Coversheet	represents a Zetafax
	coversheet.
	The <u>Coversheets</u> collection
Coversheets	
	object contains <u>Coversheet</u>
	objects.
Device	The <u>Device</u> object contains
	the configuration information
	and status of a device
	attached to the Zetafax
	server.
Devices	The <u>Devices</u> collection
	contains Device objects.
File	The File object contains the
_ <u></u>	path of a file to be attached
	to the message before it is
	sent.
Files	The Files collection object
=	contains File objects. To
	attach Zetafax attachments
	to the message use the
	Attachments collection.
The second secon	The <u>Inbox</u> object represents
	a user's Zetafax IN directory.
Letterhead	The Letterhead class
	represents a Zetafax
	letterhead.
Letterheads	The Letterheads collection
	object contains Letterhead
	objects.
Link	The Link object allows a user
' <u>⊐ LINK</u>	to retrieve information on the
	status of a link. It also
	provides statistics on the Link
	's performance.
	The Links collection contains
Links	Link objects.
	The <u>Message</u> object allows
••••••••••••••••••••••••••••••••••••••	access to the details of sent
	access to the details of sent

• <u>MessageHistories</u>	and received messages. The <u>MsgHistories</u> collection represents a message's transmission history and contains <u>MessageHistory</u>
MessageHistory	objects. The <u>MessageHistory</u> object contains an item in a message's transmission history.
MessageInfo	The <u>MessageInfo</u> object contains information about a
• <u>Messages</u>	single Message object The <u>Messages</u> collection contains Message objects from either a User's Inbox or
••••••••••••••••••••••••••••••••••••••	Outbox . The <u>NewMessage</u> object allows the logged on user to prepare and submit a new message to the Zetafax
Cutbox	server for sending. The <u>Outbox</u> object represents a user's Zetafax OUT directory.
Recipient	The <u>Recipient</u> object contains address details of an
T <u>Recipients</u>	addressee for whom a message is intended. The <u>Recipients</u> collection object contains Recipient objects.
Server Server	The <u>Server</u> object allows control over the Zetafax server, and access to objects
ServerInfo	describing the server's state. The <u>ServerInfo</u> object exposes the status and configuration of the Zetafax server.
Tan <u>UserSession</u>	The <u>UserSession</u> object contains details about a Zetafax user's configuration, messages and gives you the
Ta <u>ZfAPI</u>	ability to create new messages for sending. The <u>ZfAPI</u> object is the Application object of the COM version of the API, and is the

Type Definitions



EventEnum

The <u>DevStatusEnum</u> enumeration specifies the current status of a Device. The <u>EventEnum</u> enumeration specifies the event described in

only object that can be

the other objects.

created directly. You must create this object and logon before you can access any of







This object allows the API to print via the Zetafax Printer.

Groups

Operations

CancelPrint	This method cancels the API print mode.
IsComplete	This method checks if the Zetafax Printer has completed spooling the print output file.
StartPrint	This method switches the Zetafax Printer into API Print mode.

Read-only Properties

FileName

Returns the print spool filename.




Sub CancelPrint()

This method cancels the API print mode.

Remarks

When the <u>StartPrint</u> method is called, the Zetafax Printer is set to API Print mode; the next job will be treated as an API print job. If you have called <u>StartPrint</u> but an error has occurred during printing, you should call CancelPrint to clear the API print mode. Any subsequent jobs sent to the Zetafax Printer will then be handled in the usual way (e.g. they will be sent to the Zetafax Client).

See Also <u>APIPrint.StartPrint</u> , <u>APIPrint.IsComplete</u>





Property FileName As String

Returns the print spool filename.

Return Value

[out, retval] The print spool filename

Remarks

This method returns the print spool filename that was set by $\underline{\text{StartPrint}}$. See Also

APIPrint.StartPrint





Function IsComplete() As Boolean

This method checks if the Zetafax Printer has completed spooling the print output file.

Return Value

38

Completion status

Remarks

This method works by checking the lock status on the output file. If the permissions on the file are not sufficient to open for writing, the method will return access denied.





Sub StartPrint(ByVal bszFileName As String)

This method switches the Zetafax Printer into API Print mode.

Parameters

SzFileName 💙

Filename to print to

Remarks

Once this method has been called, the next print job sent to the Zetafax Printer under the current user context will be sent to the specified file. The Zetafax Client will not be launched. As soon as the Zetafax Printer begins processing the print job, the API print mode is cleared and subsequent jobs will be processed as normal.

See Also

APIPrint.IsComplete, APIPrint.CancelPrint





The Attachment object contains the name of a Zetafax attachment to be attached to a message before it is sent.

Groups

Operations



Read/Write Properties



The <u>Name</u> property returns the name of the attachment





Sub Delete()

The Delete method removes an <u>Attachment</u> item from the <u>Attachments</u> collection.

See Also Attachments , NewMessage





Property Name As String

The Name property returns the name of the attachment

Return Value

[out, retval]

The name of the attachment

See Also Attachments , <u>NewMessage</u>





The Attachments collection object contains Attachment_ objects.

Remarks

This collection contains attachment objects. These are Zetafax graphics attachments. To add files to the message use the Files collection. The Attachments collection cannot contain more than 30 objects.

Groups

Operations



Attachment to the collection.

Read-only Properties



See Also Attachment , Files





Function Add(ByVal bszFile As String) As ZfLib.Attachment

The Add method adds an Attachment to the collection.

Parameters

bszFile

The name of the attachment to be added to the collection.

Return Value

The new Attachment object

Remarks

If the attachment is taken from the Z-GRAPH directory, and is identified by it's Zetafax name, not it's file name.

See Also Attachment, **NewMessage**



ZfLib.Attachments.Count

Property Count As Long

The Count property returns the number of <u>Attachment</u> items in the collection.

Return Value

[out, retval]

The number of items in the collection





Property Item(ByVal var As Variant) As ZfLib.Attachment

The Item property returns the specified Attachment object.

Parameters

₩var

[in]

The index of the <u>Attachment</u> object to retrieve from the collection.

Return Value

The Attachment object retrieved from the collection.





The Coversheet class represents a Zetafax coversheet.

Groups

Read-only Properties



The <u>Name</u> property returns the name of the Coversheet.



Property Name As String

The Name property returns the name of the Coversheet.

Return Value

[out, retval]

See Also Coversheets



ZETA/AX°



The Coversheets collection object contains Coversheet objects.

Groups

Read-only Properties

🖻 <u>Count</u>	The <u>Count</u> property returns the
	number of <u>Coversheet</u> items in
	the collection.
🖻 <u>Item</u>	The <u>Item</u> property returns a
	coversheet item from the
	collection.

See Also Coversheet , ServerInfo





Property Count As Long

The Count property returns the number of <u>Coversheet</u> items in the collection.

Return Value

[out, retval]

The number of coversheet items in the Coversheets collection

See Also

<u>ServerInfo</u>, <u>Coversheet</u>





Property Item(ByVal var As Variant) As ZfLib.Coversheet

The Item property returns a coversheet item from the collection.

Parameters

bvar

[in]

The index of the coversheet to retrieve from the collection.

Return Value

The Coversheet object retrieved from the Coversheets collection

Remarks

The <u>Coversheets</u> property needs to be called using the <u>ServerInfo</u> object to retrieve an updated version of the <u>Coversheets</u> collection.

Also See: Coversheet, ServerInfo





The Device object contains the configuration information and status of a device attached to the Zetafax server.

Groups

Read-only Properties



MsgBody

The <u>CurrentPage</u> property returns the current page being sent by the device. The <u>MsgBody</u> property returns the body of the file name of the control file currently

44 Zetafax 2012 API Help

1	Name	being processed by the device. The <u>Name</u> property returns the name of
	vanie	the device. This comprises the Device Type
		and Device Number separated by a
		hyphen. An Example of a Device name
		might be FLASS-3.
.		The <u>NumConnectFails</u> property returns the
er i	<u>NumConnectFails</u>	number of send attempts by the device that
		failed to connect.
- 61		The <u>NumPages</u> property returns the
er i	<u>NumPages</u>	number of pages in the message currently
		being processed.
1		The NumSendFails returns the number of
sr i	NumSendFails	
		send attempts that failed after the device
		connected successfully.
s i	NumSendOK	The <u>NumSendOK</u> property returns the
		number of messages the device has sent
		successfully.
P	<u>Status</u>	The <u>Status</u> property returns the current
-		status of the Device object.
8	<u>User</u>	The <u>User</u> property returns the Username of
	<u></u>	the owner of the message currently being
		processed by the device.





Property CurrentPage As Short

The CurrentPage property returns the current page being sent by the device.

Return Value

[out, retval]

The current page being sent by the device.

See Also Devices





Property MsgBody As String

The MsgBody property returns the body of the file name of the control file currently being processed by the device.

Return Value

[out, retval]

The body name of the message control file

Remarks

Message bodies are made up of a "~", a four letter identifier, and a three letter/digit unique number. An example of a message body might be ~ZAPI001.

Also See: Devices





Property Name As String

The Name property returns the name of the device. This comprises the <u>Device</u> Type and <u>Device</u> Number separated by a hyphen. An Example of a <u>Device</u> name might be FLASS-3.

Return Value

[out, retval] The name of the device

Remarks

Also See: Devices



Property NumConnectFails As Short

The NumConnectFails property returns the number of send attempts by the device that failed to connect.

Return Value

[out, retval]

The number of send attempts by the device that failed because of connection problems.



equisys

ΖΕΤΑΤΑΧ



Property NumPages As Short

The NumPages property returns the number of pages in the message currently being processed.

Return Value

[out, retval]

The number of pages in the message currently being processed.

Remarks

The coversheet is included in the number of pages being sent.





Property Route As RouteEnum

The Route property returns the route type used to send a message.

Return Value

[out, retval]

This is the route type used to send a message.





Property

NumSendOK As Short

The NumSendOK property returns the number of messages the device has sent successfully.

Return Value

[out, retval]

The number of messages sent successfully on the device





Property User As String

The User property returns the Username of the owner of the message currently being processed by the device.

Return Value

[out, retval]

The user configured to use the device

See Also Devices





The Devices collection contains <u>Device</u> objects.

Remarks

The collection, and the items in the collection, represent a snap-shot of the Devices' status. If you want to update the collection you need to get a new <u>ServerInfo</u> object from the <u>Server</u> object. Objects cannot be added or removed from this collection This collection cannot exceed 100 objects.

Groups

Read-only Properties

Count Count Property returns the number of Device items in the collection.
 Item The Item Property returns a device item from the collection.

See Also Device , ServerInfo , Server





48

Zetafax 2012 API Help

Property Count As Long

The Count property returns the number of <u>Device</u> items in the collection.

Return Value

[out, retval]

The number of device items in the **Devices** collection

See Also ServerInfo , Device





Property Item(ByVal var As Variant) As ZfLib.Device

The Item property returns a device item from the collection.

Parameters

₩var

[in]

The index of the device to retrieve from the collection.

Return Value

The Device object retrieved from the Devices collection

Remarks

The <u>Devices</u> property needs to be called using the <u>ServerInfo</u> object to retrieve the update version version of the <u>Devices</u> collection.

Also See: Device , ServerInfo





The File object contains the path of a file to be attached to the message before it is sent.

Groups

Operations

Delete The Delete method removes the File object from the Files collection.

Read/Write Properties

FileName The FileName property returns the path of the file to be attached.



Sub Delete()

The Delete method removes the File object from the Files collection.

See Also Files , NewMessage



equisys

ΖΈΤΑ/ΑΧ



Property FileName As String

The FileName property returns the path of the file to be attached.

Parameters

strFilename

[in]

Return Value

[out, retval]

The path of the file attached to a new message **See Also** Files , NewMessage





The Files collection object contains \underline{File} objects. To attach Zetafax attachments to the message use the <u>Attachments</u> collection.

Groups

Operations



Read-only Properties

🔊 Count	The <u>Count</u> property returns the
	number of File items in the
	collection.
🖻 <u>Item</u>	The <u>Item</u> property returns the
	specified File object.

See Also File , <u>Attachments</u>





Function Add(ByVal bszFile As String) As ZfLib.File

The Add method adds a File object to the collection.

Parameters

bszFile

The path of the file to be added to the collection.

Return Value

This method returns the new File object

Remarks

To reduce the possibility of errors, it is best to specify the full path when adding files to the collection.

See Also File , <u>NewMessage</u>





Property Count As Long

The Count property returns the number of \underline{File} items in the collection.

Return Value

[out, retval]

The number of items in the collection .





Property Item(ByVal var As Variant) As $\underline{\tt ZfLib.File}$

The Item property returns the specified File object.

Parameters

₩var

[in]

The index of the File object to retrieve from the collection.

Return Value

The File object retrieved from the collection.





The Inbox object represents a user's Zetafax IN directory.

Remarks

This object is the same as the <u>Outbox</u> object except that it points to a different folder.

Groups

Operations



the items in this directory

See Also Outbox , Messages, Message



Function CheckNewMsgStatus() As Boolean

The CheckNewMsgStatus method checks whether the status of any of the messages in the current user's IN directory have changed.

Return Value

52

Returns True if the status of any of the messages have changed

See Also ZfAPI , UserSession , Outbox



equisys

ΤΑ/ΑΧ°



Function GetMsg(ByVal bszMsg As String) As ZfLib .Message

The GetMsg method returns the Message object matching the specified message body name.

Parameters

bszMsg

The body name of the message to retrieve.

See Also Messages, Message



ZfLib.Inbox.GetMsgList

Function GetMsgList() As ZfLib .Messages

The GetMsgList method returns a Messages collection containing all the items in this directory

Return Value

The Messages collection object retrieved from the user's IN directory.

See Also Outbox , Messages





The Letterhead class represents a Zetafax letterhead.

Groups

Read-only Properties



The Name property returns the name of the Letterhead.





Property Name As String

The Name property returns the name of the Letterhead.

Return Value

[out, retval]

See Also Letterheads





The Letterheads collection object contains Letterhead objects.

Groups

Read-only Properties

54

Zetafax 2012 API Help

	The <u>Count</u> property returns the
	number of Letterhead items in the
	collection.
🖻 <u>Item</u>	The <u>Item</u> property returns a
	letterhead item from the collection.

See Also Letterhead , ServerInfo



Property Count As Long

The Count property returns the number of <u>Letterhead</u> items in the collection.

Return Value

[out, retval]

The number of letterhead items in the Letterheads collection

See Also ServerInfo , Letterhead



equisys

ΖΕΤΑ/ΑΧ



Property Item(ByVal var As Variant) As <u>ZfLib.Letterhead</u> The Item property returns a letterhead item from the collection.

Parameters

😽var

[in]

The index of the letterhead to retrieve from the collection.

Return Value

The Letterhead object retrieved from the Letterheads collection

Remarks

The <u>Letterheads</u> property needs to be called using the <u>ServerInfo</u> object to retrieve the update version version of the <u>Letterheads</u> collection.

See Also Letterhead , ServerInfo





The Link object allows a user to retrieve information on the status of a link. It also provides statistics on the Link's performance.

Groups

Read-only Properties

ConnectionOK	The <u>ConnectionOK</u> property returns the current state of the connection to the
is a state of the	Remote server. The <u>LinkActive</u> property returns the active status of the Link.
LocalStatus	The <u>LocalStatus</u> property retrieves the current status of the link.
Part NumAcknowledged	The <u>NumAcknowledged</u> property returns the number of messages that have been submitted to the Remote server and have
MumDeviceError	been acknowledged. The <u>NumDeviceError</u> property returns the number of messages that failed to be sent as a result of device errors.
MumReceived	The <u>NumReceived</u> property returns the number of messages that have been received from the Remote server for
MumRejected	sending locally. The <u>NumRejected</u> property returns the number of messages rejected by the Remote server.
MumRemoteServerError	The <u>NumRemoteServerError</u> property returns the number of messages that failed to be sent as a result of other
MumSentOK	errors at the Remote server. The <u>NumSentOK</u> property returns the number of messages sent successfully by the Remote server.
NumTimedOut	The <u>NumTimedOut</u> property returns the number of messages that timed out while
MumUnAcknowledged	waiting for a response over the link. The <u>NumUnAcknowledged</u> property returns the number of messages that
Part RemoteServer	haven't been acknowledged. The <u>RemoteServer</u> property returns the name of the Remote server to which the link is configured.
Participation Provide America	The <u>RemoteStatus</u> property returns the current status of the remote server.



Property ConnectionOK As Boolean

The ConnectionOK property returns the current state of the connection to the Remote server.

Return Value

[out, retval]

This property returns the state of the connection. True if it is OK, False otherwise.

See Also Links



Property LinkActive As Boolean

The LinkActive property returns the active status of the Link .

Return Value

[out, retval]

Returns True to indicate the link is active and available for sending and receiving, otherwise it returns False.

See Also Links





Property

LocalStatus As LinkStatusEnum

The LocalStatus property retrieves the current status of the link.







equisys

ΖΕΤΑΤΑΧ

Return Value

[out, retval] This is the current status of the link on the local server.

See Also Links , LinkStatusEnum



Property NumAcknowledged As Short

The NumAcknowledged property returns the number of messages that have been submitted to the Remote server and have been acknowledged.

Return Value

[out, retval]

The number of messages submitted that have been acknowledged.

See Also Links





Property NumDeviceError As Short

The NumDeviceError property returns the number of messages that failed to be sent as a result of device errors.

Return Value

[out, retval]

The number of device errors that occurred on the Remote server

See Also Links



Property NumReceived As Short

The NumReceived property returns the number of messages that have been received from the Remote server for sending locally.

Return Value

[out, retval]

The number of messages received from the Remote server

See Also Links



Property NumRejected As Short

The NumRejected property returns the number of messages rejected by the Remote server.

Return Value

[out, retval]

The number of messages rejected by the Remote server.

See Also Links





Property NumRemoteServerError As Short

The NumRemoteServerError property returns the number of messages that failed to be sent as a result of other errors at the Remote server.

Return Value

[out, retval]



equisys

Ζέτα Άχ

ΖΕΤΑ/ΑΧ

equisys

The number of Remote server errors on this link See Also Links



Property NumSentOK As Short

The NumSentOK property returns the number of messages sent successfully by the Remote server.

Return Value

[out, retval]

The number of messages sent successfully by the Remote server

See Also Links





Property NumTimedOut As Short

The NumTimedOut property returns the number of messages that timed out while waiting for a response over the link.

Return Value

[out, retval]

The number of messages timed out on the link





Property NumUnAcknowledged As Short

The NumUnAcknowledged property returns the number of messages that haven't been acknowledged.

Return Value

Zetafax 2012 API Help

[out, retval]

The number of messages awaiting acknowledgedment.

See Also Links



Property

RemoteServer As String

The RemoteServer property returns the name of the Remote server to which the link is configured.

Return Value

[out, retval] The name of the remote server



equisys

ΖΕΤΑΤΑΧ



Property RemoteStatus As LinkStatusEnum

The RemoteStatus property returns the current status of the remote server.

Return Value

[out, retval]

The current status of the Remote server

See Also Links , LinkStatusEnum





The Links collection contains Link objects.

Remarks

The collection, and the items in the collection, represent a snap-shot of the Links' status. If you want to update the collection you need to get a new <u>ServerInfo</u> object from the Server object.

Objects cannot be added to or removed from this collection.

Groups

Read-only Properties

Count The Count property returns the total number of Link items in the collection.
 Item The Item property returns the specified Link object.

See Also Link , ServerInfo , Server





Property Count As Long

The Count property returns the total number of Link items in the collection.

Return Value

[out, retval]

The number of Link items in the Links collection

See Also

Link , ServerInfo





Property Item(ByVal var As Variant) As ZfLib.Link

The Item property returns the specified Link object.

Parameters

💙var

[in]

62

The index of the $\underline{\mathsf{Link}}$ object to retrieve from the collection.

Return Value

The <u>Link</u> object retrieved from the <u>Links</u> collection.

See Also Link , ServerInfo





The Message object allows access to the details of sent and received messages.

Remarks

You can use this object to delay or rush messages that have not yet been sent.

To create a new message you have to use the NewMessage $% \mathcal{A}$ object returned by UserSession. CreateNewMsg .

Groups

Operations

AbortMsgDeleteMsg	The <u>AbortMsg</u> method aborts the sending of a message. The Delete method removes an entry of the message from the IN or OUT
GetMsgHistories	message information file. The <u>GetMsgHistories</u> method returns the MessageHistories collection containing the transmission history of
GetMsgInfo	the message. The <u>GetMsgInfo</u> method returns the MessageInfo object. This allows access to information about a message.
🖗 <u>HoldMsg</u>	The <u>HoldMsg</u> method holds the sending of the current message.
MarkMsgAsRead	The <u>MarkMsgAsRead</u> method changes the 'user status' of a message to 'OK'. This will make it appear as 'read' to client programs.
ReleaseMsg	The <u>ReleaseMsg</u> method releases a held message and places it in the message queue for sending.
RushMsg	The <u>RushMsg</u> method is used to rush a message for sending.
SendMsg	The <u>SendMsg</u> method places a message in the message queue for sending by the Zetafax server.

See Also NewMessage





Sub AbortMsg()

The AbortMsg method aborts the sending of a message.

See Also Messages





Sub DeleteMsg(ByVal fDeleteFiles As Boolean)

The Delete method removes an entry of the message from the IN or OUT message information file.

Parameters

➡fDeleteFiles

Boolean flag to delete associate data files if True.

Remarks

The Delete method removes the object from the collection. If you have another reference to the object it's properties and methods may return errors.





ZfLib.Message.GetMsgHistories

Function GetMsgHistories() As ZfLib.MessageHistories

The GetMsgHistories method returns the <u>MessageHistories</u> collection containing the transmission history of the message.

Return Value

The retrieved MessageHistories collection.

See Also Messages



Function GetMsgInfo() As ZfLib.MessageInfo

The GetMsgInfo method returns the <u>MessageInfo</u> object. This allows access to information about a message.

Return Value

The retrieved MessageInfo object.

See Also Messages



equisys

ΖέτΑ ΑΧ



Sub HoldMsg()

The HoldMsg method holds the sending of the current message.

See Also Messages, Inbox





Sub MarkMsgAsRead()

The MarkMsgAsRead method changes the 'user status' of a message to 'OK'. This will make it appear as 'read' to client programs.

See Also Messages, Inbox





Sub ReleaseMsg()

The ReleaseMsg method releases a held message and places it in the message queue for sending.

See Also Messages, Inbox



Sub RushMsg()

The RushMsg method is used to rush a message for sending.

See Also Messages



ΖΕΤΑΤΑΧ

equisys



Sub SendMsg()

The SendMsg method places a message in the message queue for sending by the Zetafax server.

See Also Messages, Inbox





The MsgHistories collection represents a message's transmission history and contains MessageHistory objects.

Remarks

The collection, and the items in the collection, represent a snap-shot of the message's history. If you want to update the collection you need to get a new MessageHistories object from it's parent Message object.

Objects cannot be added or removed from this collection.

Groups

66

Zetafax 2012 API Help

Read-only Properties

🖻 <u>Count</u>	The <u>Count</u> method returns the number of MessageHistory
i <mark>∐tem</mark>	items in the collection. The <u>Item</u> property returns a MessageHistory item from the collection.

See Also MessageHistory, Message, MessageInfo





Property Count As Long

The Count method returns the number of <u>MessageHistory</u> items in the collection.

Return Value

[out, retval]

The number of <u>MessageHistory</u> items in the collection.

See Also Message, MessageHistory



ZfLib.MessageHistories.Item

Property Item(ByVal var As Variant) As ZfLib.MessageHistory

The Item property returns a MessageHistory item from the collection.

Parameters

😽var

[in]

The <u>MessageHistory</u> item to retrieve from the <u>MessageHistories</u> collection.

Return Value

The <u>MessageHistory</u> object retrieved from the collection.

See Also Message, MessageHistory



ZfLib.MessageHistory

The MessageHistory object contains an item in a message's transmission history.

Groups

Read-only Properties

i [™] <u>AddrNum</u>	The <u>AddrNum</u> property returns addressee number starting from 1. This allows events to be matched to addressees when a single message has been sent to more than one person.
Provide a connection	The <u>Connection</u> property returns the connection time in seconds.
嶜 <u>Date</u>	The <u>Date</u> property returns the transmission date of the message.
🖻 <u>Device</u>	The <u>Device</u> property returns the name of the device used to send the message.
ErrorCode	The <u>ErrorCode</u> property returns the reason an attempt to send a message failed.
🚰 <u>Event</u>	The <u>Event</u> property returns the Event type of this MessageHistory object.
[™] <u>Name</u>	The <u>Name</u> property returns the name of the recipient associated with this
Prganisation	MessageHistory event The <u>Organisation</u> property returns the organisation of the recipient associated with this MessageHistory event
PagesSent	The <u>PagesSent</u> property returns the last page successfully sent.
PremoteServer <u>RemoteServer</u>	The <u>RemoteServer</u> property returns the name of the remote server used to send a
	message when the message was sent using LCR.
Proute <u>Route</u>	The <u>Route</u> property returns the route type used to send a message.
Params <u>RouteParams</u>	The <u>RouteParams</u> property returns the route parameters used. For fax routes this is the fax number dialled.





Property AddrNum As Short

The AddrNum property returns addressee number starting from 1. This allows events to be matched to

68

Zetafax 2012 API Help

addressees when a single message has been sent to more than one person.

Return Value

[out, retval]

The addressee index.

See Also Messages, MessageHistories





Property Connection As Short

The Connection property returns the connection time in seconds.

Return Value

[out, retval]

The connection time in seconds

See Also

Messages, MessageHistories





Property Date As Date

The Date property returns the transmission date of the message.

Return Value

[out, retval]

The date the message was sent

See Also

Messages, MessageHistories





Property Device As String

The Device property returns the name of the device used to send the message.

Return Value

[out, retval]

The name of the device used

See Also

Messages, MessageHistories





Property ErrorCode As Long

The ErrorCode property returns the reason an attempt to send a message failed.

Return Value

[out, retval]

The returned Error code as a result of failure.

Remarks

Note that the values returned depend on the version of Zetafax Server running, not the version of API used. Newer version of the server will have additional error codes added.

See Also ZfErr , <u>Messages</u>, <u>MessageHistories</u>





Property Event As EventEnum

The Event property returns the Event type of this <u>MessageHistory</u> object.

Return Value

[out, retval]

The retrieved EventEnum value.

See Also Messages, Message, EventEnum





Property Name As String

The Name property returns the name of the recipient associated with this MessageHistory event

Return Value

[out, retval]

The name of the Remote server used

See Also

Messages, MessageHistories





Property Organisation As String

The Organisation property returns the organisation of the recipient associated with this <u>MessageHistory</u> event

Return Value

[out, retval]

The name of the Remote server used

See Also Messages, MessageHistories





Property PagesSent As Short

The PagesSent property returns the last page successfully sent.

Return Value

[out, retval]

The last page number sent

Remarks

If a three page message had several attempts at sending but only first two pages were sent successfully, this value would be set to 2.

See Also Messages, MessageHistories





Property RemoteServer As String

The RemoteServer property returns the name of the remote server used to send a message when the message was sent using LCR.

Return Value

[out, retval]

The name of the Remote server used

See Also Messages, MessageHistories





Property Route As RouteEnum

The Route property returns the route type used to send a message.

Return Value

[out, retval]

This is the route type used to send a message.



Property RouteParams As String

The RouteParams property returns the route parameters used. For fax routes this is the fax number dialled.

Return Value

[out, retval]

The route parameters used to send a message.

See Also Messages, MessageHistories



ZETA/AX°



The MessageInfo object contains information about a single Message object.

Groups

Read-only Properties

I Body I <u>Comment</u> I CustomField	The <u>Body</u> property returns the body name of the message's files. The <u>Comment</u> property returns the comment associated with the message. The <u>CustomField</u> property returns the custom field data associated with the message.
ImageSize	
<u> </u>	
Organisation	The Organisation property returns the organisation of the first recipient to which this fax was sent. It is
[™] <u>Status</u> [™] <u>Subject</u>	therefore only used in the Out directory. The <u>Status</u> property returns the status of a message. The <u>Subject</u> property returns the subject of the
73

message. The \underline{Type} property returns the type of message you are looking at. The UserStatus property returns the 'user status' of a Interest and a series of the s message.

See Also Message, MessageHistory

🚰 <u>Туре</u>





Property Attachments As ZfLib.Attachments

This property retrieves the Attachments collection.

Return Value

[out, retval]

The retrieved Attachments collection

Remarks

If ZfLib.Attachments.Count returns 0 there are no attachments associated with the fax.



Property Body As String

The Body property returns the body name of the message's files.

Return Value

[out, retval]

The message body name

See Also Messages, Message





Property Comment As String

The Comment property returns the comment associated with the message.

Return Value

[out, retval]

The Comment line of a message





Property CoverText As String

The CoverText property returns the covertext of the message

Return Value

[out, retval]

The covertext of a message





Property CustomField As String

The CustomField property returns the custom field data associated with the message.





Property Files As ZfLib.Files
This property retrieves the Files collection
Return Value
[out, retval]
The retrieved Files collection
Remarks
If ZfLib.Files.Count returns 0 no files were attached to the fax.



equisys



Property ImageFilePath As String



Property ImageSize As Long



ZETA/AX

ΖΕΤΑ ΑΧ



Property ImageStream As IStream



Property Organisation As String

The Organisation property returns the organisation of the first recipient to which this fax was sent. It is therefore only used in the Out directory.

Return Value

[out, retval]

The name of the Organisation to which this message was sent



Property Status As StatusEnum

The Status property returns the status of a message.

Return Value

[out, retval]

The status of a message.



Property Subject As String

The Subject property returns the subject of the message.

Return Value

[out, retval]

The Subject line of a message

See Also Messages, Message





Property Type As FaxTypeEnum

The Type property returns the type of message you are looking at.



equisys

Ζέτα/ΑΧ

Return Value

[out, retval]

The type of message at which you are looking

RemarksNote: This field defaults to type zfFaxTypeFax.

See Also FaxTypeEnum, Message





Property UserStatus As <u>UserStatusEnum</u>

The UserStatus property returns the 'user status' of a message.

Return Value

[out, retval]

The 'user status' of a message.

Remarks

The 'user satus' refers to the user's awareness of the message rather than the actual 'status' of the message ('read' or 'unread' rather than 'OK' or 'Failed').





The Messages collection contains Message objects from either a User's Inbox or Outbox.

Remarks

You do not add objects to the collection directly. To add an item to the \underline{Inbox} you must send a fax, and add an item in the \underline{Outbox} you must receive a fax.

This collection can contain thousands of objects.

Groups

Read-only Properties

প্রে <u>Count</u>	The <u>Count</u> property returns the
— <u>count</u>	number of Message items in the
	collection.
🗐 Item	The <u>Item</u> method retrieves a
— <u>Item</u>	Message item from the collection.

Zetafax 2012 API Help



78

The <u>MsqDir</u> property returns the full path of the directory which holds the messages in this collection.





Property Count As Long

The Count property returns the number of <u>Message</u> items in the collection.

Return Value

[out, retval]

The number of Message items in the Messages collection.

See Also Inbox , Outbox





Property Item(ByVal var As Variant) As ZfLib .Message

The Item method retrieves a Message item from the collection.

Parameters

₩var

[in]

The index of the Message object we wish to retrieve from the collection

Return Value

The Message object retrieved from the Messages collection

See Also Inbox , Outbox





Property MsgDir As String

The MsgDir property returns the full path of the directory which holds the messages in this collection.

Return Value

[out, retval]

The retrieved message directory

See Also Inbox , Outbox , Messages





The NewMessage object allows the logged on user to prepare and submit a new message to the Zetafax server for sending.

Remarks

At least one Recipient must be configured before sending. The message is sent using a submit file.

Groups

Operations

Send The Send method submits the prepared message to the Zetafax server for sending.

Read-only Properties

Attachments	This property retrieves the <u>Attachments</u> collection used to add
	Zetafax attachments to the new
	message.
🖻 Body	After a message has been sent
_ <u>body</u>	successfully this property contains
	the message body name. This is
	useful when you wish to keep track
	of the message in the <u>Outbox</u> .
🚰 Files	This property retrieves the Files
	collection.
Recipients	This property retrieves the
	Recipients collection.

#Read/Write Properties

🖻 <u>After</u>	The <u>After</u> property specifies the time and date after which the message is to be sent.
曾 <u>Charge</u> 曾 <u>Comment</u>	The <u>Charge</u> property specifies the billing code to use for a message. The <u>Comment</u> property specifies the message description usually
[™] <u>CoverSheet</u>	displayed on the right of the Zetafax client OUT window. The <u>CoverSheet</u> property specifies the Coversheet to be added to the new message.
🚰 <u>Covertext</u>	The <u>Covertext</u> property specifies the text to be added to the selected
Pelete <u>Delete</u>	coversheet. The <u>Delete</u> property specifies whether the server should delete the message from the OUT folder
🖻 <u>Format</u> 🖻 From	after it has been sent. This property specifies the file format of the data file to be sent. The <u>From</u> property specifies the
Header	name that is put on the message <u>Coversheet</u> as the sender of the message. The <u>Header</u> property specifies the
	format of the <u>Header</u> line to appear at the top of each page of the message.
🔊 <u>Hold</u>	The <u>Hold</u> property specifies whether the message will be held once it is in the queue, i.e. it will not be sent until the user releases it.
Paraget <u>Letterhead</u>	The <u>Letterhead</u> property specifies a file (<u>Letterhead</u>) on which to merge the message before sending.
Preview Preview	The <u>Preview</u> property specifies whether a preview file is to be prepared for the message.
Priority	This property specifies priority of the message.
🖻 <u>Quality</u>	The <u>Quality</u> property specifies the resolution to be used when sending the message.
SendTime	The <u>SendTime</u> property specifies when the message should be sent.
Part Subject	The <u>Subject</u> property specifies a message Subject line, which is displayed on the coversheet an in
i <mark>⊡</mark> <u>Text</u>	the Zetafax Client's out window. The <u>Text</u> property specifies the Text of the new message.
🚰 <u>User</u>	The <u>User</u> property specifies the Zetafax user submiting the message.
[™] <u>CustomField</u>	The Custom Field property allows users of the API to specify their own custom data





Property After As Date

The After property specifies the time and date after which the message is to be sent.

Parameters

⇒after

[in]

The date and time to send a message.

Return Value

[out, retval]

The date and time to send the new message.

Remarks

This field is only used when the <u>SendTime</u> property is set to *zfSendTimeAfter*.

See Also SendTime





Property Attachments As ZfLib.Attachments

This property retrieves the Attachments collection used to add Zetafax attachments to the new message.

Return Value

[out, retval]

The retrieved Attachments collection.

Remarks

A new message does not need to contain any attachments.

See Also

82

Zetafax 2012 API Help

Attachment , NewMessage , Files





Property Body As String

After a message has been sent successfully this property contains the message body name. This is useful when you wish to keep track of the message in the Outbox .

Return Value

[out, retval]

The retrieved message body.

See Also Outbox.GetMsg





ZfLib.NewMessage.Charge

Property Charge As String

The Charge property specifies the billing code to use for a message.

Parameters

strCharge

[in]

Return Value

[out, retval]

The charge code used for a message.

Remarks

The charge codes are stored in the billing log when the fax completes, and may be used for charging the fax to a particular department/client.



ZfLib.NewMessage.Comment

Property Comment As String

The Comment property specifies the message description usually displayed on the right of the Zetafax client OUT window.

Parameters

strComment

[in]

Return Value

[out, retval]

The retrieved Comment line of the message.

Remarks

If the Comment line is omitted a message description detailing the first addressee is used.





Property CoverSheet As String

The CoverSheet property specifies the <u>Coversheet</u> to be added to the new message.

Parameters

strCoverSheet

[in]

Return Value

[out, retval]

The CoverSheet used with the message.

Remarks

To specify the coversheet use the name by which it is known in Zetafax, not it's file name.



Property Covertext As String

The Covertext property specifies the text to be added to the selected coversheet.

Parameters

StrCovertext

[in]

Return Value

[out, retval]

The Covertext to be inserted onto the coversheet.

See Also CoverSheet





Property CustomField As String

The Custom Field property allows users of the API to specify their own custom data





Property Delete As Boolean

The Delete property specifies whether the server should delete the message from the OUT folder after it has been sent.

Parameters

♦fDelete

[in]

Return Value

[out, retval] The retrieved Delete flag.





Property Files As ZfLib.Files

This property retrieves the Files collection.

Return Value

[out, retval]

The retrieved Files collection.

Remarks

A new message does not need to contain any files.

See Also File , NewMessage , Attachments





Property Format As FormatEnum

This property specifies the file format of the data file to be sent.

Parameters

₩format

[in]

The Format type to use for this message

Return Value

[out, retval]

Remarks

In a standard submit file the format should be "ASCII" or "EPSON". Epson should be used if the message text contains any %% formatting commands, for

Zetafax 2012 API Help

example

%%[BOLD: ON]

See Also FormatEnum



Property From As String

The From property specifies the name that is put on the message Coversheet as the sender of the message.

Parameters

strFrom

[in]

Return Value

[out, retval]

The current From line of the new message



equisys

ZÉTA/AX°



Property Header As HeaderEnum

The Header property specifies the format of the Header line to appear at the top of each page of the message.

Parameters

😒 header

[in]

The new Header type to use for this message

Return Value

[out, retval]

The current Header type of this message

equisys

ΖΕΤΑΤΑΧ

Remarks

Specify more than one field OR the values together as for example:

zfHeaderNumber Or zfHeaderTo

See Also HeaderEnum



Property Hold As Boolean

The Hold property specifies whether the message will be held once it is in the queue, i.e. it will not be sent until the user releases it.

Parameters

₩fHold

[in]

Whether we want to hold this message.

Return Value

[out, retval]

Whether this message is to be held.

See Also

Message.Hold, Message.Release





Property

Letterhead As String

The Letterhead property specifies a file (Letterhead) on which to merge the message before sending.

Parameters

strLetterhead [in]

Return Value

88 Zetafax 2012 API Help

[out, retval] The current Letterhead to be used for this message.

Remarks

To specify the letterhead use the name by which it is known in Zetafax, not it's file name.



Property Preview As Boolean

The Preview property specifies whether a preview file is to be prepared for the message.

Return Value

[out, retval]

Whether we currently want a message preview.



equisys

Ζέτα ΤΑΧ



Property Priority As PriorityEnum This property specifies priority of the message.

Parameters

bpriority

[in]

This is the new Priority of the message

Return Value

[out, retval]

The current Priority of the message

See Also NewMessage , PriorityEnum





Property Quality As QualityEnum

The Quality property specifies the resolution to be used when sending the message.

Parameters

****quality

[in]

The new resolution with which to send this message

Return Value

[out, retval]

The current resolution the message

See Also NewMessage , QualityEnum



Property Recipients As ZfLib.Recipients

This property retrieves the Recipients collection.

Return Value

[out, retval]

The retrieved Recipients collection.

Remarks

The recipients object must contain one or more recipients otherwise the sending of the message will fail.

See Also NewMessage , Recipient

ZfLib.NewMessage.Send

Sub Send()

The Send method submits the prepared message to the Zetafax server for sending.

Remarks

At least one recipient should be specified for this method to succeed.





Property SendTime As SendTimeEnum

The SendTime property specifies when the message should be sent.

Parameters

sendTime

[in]

The new SendTime of the message.

Return Value

[out, retval]

The current SendTime of the message.

Remarks

If SendTime is set to *zfSendTimeAfter* then you need to specify the time to send using the After property.

See Also After





Property Subject As String

The Subject property specifies a message Subject line, which is displayed on the coversheet an in the

Zetafax Client's out window.

Parameters

StrSubject

[in]

Return Value

[out, retval]

The retrieved Subject line this message

Remarks

The maximum subject field is 60 characters long.





Property Text As String

The Text property specifies the Text of the new message.

Parameters

⇒strText

[in]

Return Value

[out, retval]

The retrieved body text of the new message.





Property User As String

The User property specifies the Zetafax user submiting the message.

Parameters

strUser

[in]

Return Value

[out, retval]

The current User submiting this message

See Also UserSession





The Outbox object represents a user's Zetafax OUT directory.

Remarks

This object is the same as the Inbox object except that it points to a different folder.

Groups

Operations

CheckNewMsgStatus	The <u>CheckNewMsgStatus</u> method checks whether the status of any of the messages in
GetMsg	the current user's OUT directory have changed. The <u>GetMsg</u> method returns the Message object matching the specified message body
	name. The <u>GetMsgList</u> method returns a Messages collection containing all the items in this directory

See Also Inbox , Messages, Message





Function CheckNewMsgStatus() As Boolean

The CheckNewMsgStatus method checks whether the status of any of the messages in the current user's OUT directory have changed.

Return Value

Returns True if there are new messages or a message's status has changed

See Also ZfAPI , UserSession , Inbox



ZfLib.Outbox.GetMsg

Function GetMsg(ByVal bszMsg As String) As ZfLib .Message

The GetMsg method returns the Message object matching the specified message body name.

Parameters

bszMsg

The body name of the message to retrieve

See Also Messages, Message





Function GetMsgList() As ZfLib .Messages

The GetMsgList method returns a Messages collection containing all the items in this directory

Return Value

The retrieved Messages object.

See Also Inbox , Messages





The Recipient object contains address details of an addressee for whom a message is intended.

Remarks

Both the <u>To</u> and <u>Fax</u> properties need to be specified prior to sending a message.

If you use <u>Recipients</u> various Add methods you will not need to access this object directly.

94

Groups

Operations

Delete

The <u>Delete</u> method removes this recipient from the <u>Recipients</u> collection.

Read/Write Properties

The Fax property retrieves the Fax number of the recipient of a
message.
This property specifies the
organisation to which the recipient
belongs.
This property specifies the
recipient's name.
The <u>Type</u> property specifies how the message will be sent to the recipient.

See Also
<u>NewMessage</u>, <u>Recipients.AddFaxRecipient</u>, <u>Recipients.AddLANRecipient</u>





Sub Delete()

The Delete method removes this recipient from the Recipients collection.

See Also Recipients , NewMessage





Property Fax As String

The Fax property retrieves the Fax number of the recipient of a message.

Parameters

strFax

[in]

This is the new Fax number of the recipient.

Return Value

[out, retval]

The current Fax number of the recipient.

Remarks

This field could perhaps be better described as the address. If we were sending a LAN type address then the Fax property would actually contain the Zetafax user name of the person being sent the fax.

See Also Recipients





Property Organisation As String

This property specifies the organisation to which the recipient belongs.

Parameters

StrOrganisation

[in]

The new Organistaion name of the recipient.

Return Value

[out, retval]

The current organisation name.





Property To As String

This property specifies the recipient's name.

Parameters

strRecipient

[in]

The name of the recipient of the new message.

Return Value

[out, retval]

The current name of the recipient.



Property Type As FaxTypeEnum

The Type property specifies how the message will be sent to the recipient.

Parameters

♦faxType

[in]

The new way the message will be sent.

Return Value

[out, retval]

The current way the message will be sent.

See Also Recipients , FaxTypeEnum



equisys

ΖΈΤΑ/ΑΧ



The Recipients collection object contains **<u>Recipient</u>** objects.

Remarks

This collection cannot exceed 30 objects.

New objects are added using the various AddRecipient methods which create a properly configured Recipient object. This means you will rarely have to access a recipient object directly.

Groups

Operations

97

- AddFaxRecipient
- AddLANRecipient
- AddSMSRecipient

The <u>AddFaxRecipient</u> method adds a Fax Recipient item to the collection. The <u>AddLANRecipient</u> method adds a LAN Recipient item to the collection. The <u>AddSMSRecipient</u> method adds an SMS Recipient item to the collection.

Read-only Properties

<u>Count</u>
 <u>The Count</u> method returns the number of Recipient items in the collection.
 <u>Item</u>
 <u>The Item</u> property retrieves a Recipient item from the collection.

See Also Recipient



ZfLib.Recipients.AddFaxRecipient

Function AddFaxRecipient(ByVal bszTo As String, ByVal bszOrganisation As String, ByVal bszFax As String) As <u>ZfLib.Recipient</u>

The AddFaxRecipient method adds a Fax Recipient item to the collection.

Parameters

≫bszTo

The name of the recipient.

bszOrganisation

The name of the organnisation to which the recipient belongs.

bszFax

The recipient's Fax Number.

Return Value

The new <u>Recipient</u> object.

See Also NewMessage , FaxTypeEnum



ZfLib.Recipients.AddLANRecipient

Function AddLANRecipient(ByVal bszTo As String, ByVal bszOrganisation As String, ByVal bszUser As String) As <u>ZfLib.Recipient</u>

The AddLANRecipient method adds a LAN Recipient item to the collection.

Parameters

bszTo
The name of the recipient.

bszOrganisation The name of the organnisation which the recipient belongs.

bszUser The LAN Address of the recipient.

Return Value

The new Recipient object.

See Also NewMessage , Recipients.AddFaxRecipient , FaxTypeEnum





Function AddSMSRecipient(ByVal bszTo As String, ByVal bszOrganisation As String, ByVal bszSMS As String) As <u>ZfLib.Recipient</u>

The AddSMSRecipient method adds an SMS Recipient item to the collection.

Parameters

bszTo
The name of the <u>Recipient</u>.

bszOrganisation The organisation to which the recipient belongs.

bszSMS The SMS number of the recipient.

Return Value

The new Recipient object.

See Also
<u>NewMessage</u>, <u>Recipients.AddFaxRecipient</u>, <u>FaxTypeEnum</u>





Property Count As Long

The Count method returns the number of Recipient items in the collection.

Return Value

[out, retval]

The number of items in the Recipients collection





Property Item(ByVal var As Variant) As ZfLib.Recipient

The Item property retrieves a <u>Recipient</u> item from the collection.

Parameters

var

[in]

The index of the item to retrieve from the collection.

Return Value

The <u>Recipient</u> object retrieved from the <u>Recipients</u> collection.





The Server object allows control over the Zetafax server, and access to objects describing the server's state.

Groups

100 Zetafax 2012 API Help

_								
0	In	0	12	C	÷i	\sim	n	C
\sim	U	c		а	u	U		3

	This is a method to check if the Zetafax server is running.
GetServerInfo	The <u>GetServerInfo</u> method returns the <u>ServerInfo</u> object which contains information about the state of the Zetafax server.
Restart	This method restarts the Zetafax Server.
	This method starts the Zetafax Server if it is stopped.
♦ <u>Stop</u>	This method stops the Zetafax Server if it is running.

See Also ServerInfo





Function Check() As Boolean

This is a method to check if the Zetafax server is running.

Return Value

If the server is running this method returns True.





Function GetServerInfo() As <u>ZfLib.ServerInfo</u>

The GetServerInfo method returns the ServerInfo object which contains information about the state of the Zetafax server.

Return Value

This method returns the <u>ServerInfo</u> object.





Sub Restart()

This method restarts the Zetafax Server.





Sub Start()

This method starts the Zetafax Server if it is stopped.





Sub Stop()

This method stops the Zetafax Server if it is running.



ZfLib.ServerInfo

The ServerInfo object exposes the status and configuration of the Zetafax server.

Groups

Read-only Properties

[™] <u>Coversheets</u>	The <u>Coversheets</u> property returns a <u>Coversheets</u> collection with information about the <u>Coversheets</u> on the Zetafax
[™] Deferred	server. The deferred property retrieves the number of items in the queue that have been deferred.
<u> </u>	The <u>Devices</u> property returns a Devices collection detailing the current state of
[™] Letterheads	the Zetafax server's devices. The <u>Letterheads</u> property returns a <u>Letterheads</u> collection with information about the Letterheads on the Zetafax
₪ <mark>Links</mark>	server. The <u>Links</u> property returns a Links collection with information about the

102 Zetafax 2012 API Help

	current state of the LCR links maintianed by the Zetafax server.
MaxDevices	The <u>MaxDevices</u> property retrieves the maximum number of devices the
MaxLinks	Zetafax server supports. The <u>MaxLinks</u> property retrieves the maximum number of LCR links the
RemoteAccept	Zetafax server supports. The <u>RemoteAccept</u> property retrieves the number of message items currently
	accepted for sending by remote servers. The <u>RouterSub</u> property retrieves the number of items submitted to the Router
	for sending and awaiting acceptance by a remote server.
Scanning	The <u>Scanning</u> property retrieves the number of items in the queue being
[™] Sending	processed by a scanning device. The <u>Sending</u> property returns the number of items in the queue which are
[™] <u>WaitingConvert</u>	currently being sent. The <u>WaitingConvert</u> property retrieves the number of items in the queue
	waiting to be converted or being prepared for sending.
[™] <u>WaitingDevice</u>	The <u>WaitingDevice</u> property retrieves the number of items waiting for a device
MaitingResend	to become available. The <u>WaitingResend</u> property retrieves the number of items in the queue
	waiting before retrying after a send attempt failed.





Property Coversheets As ZfLib.Coversheets

The Coversheets property returns a Coversheets collection with information about the Coversheets on the Zetafax server.

Return Value

[out, retval]

The Coversheets collection.

See Also Coversheets, Coversheet





Property Deferred As Short

The deferred property retrieves the number of items in the queue that have been deferred.

Return Value

[out, retval]

The number of deferred message items.





Property Devices As ZfLib.Devices

The Devices property returns a Devices collection detailing the current state of the Zetafax server's devices.

Return Value

[out, retval]

The Devices collection.

See Also Devices





Property Letterheads As ZfLib.Letterheads

The Letterheads property returns a Letterheads collection with information about the Letterheads on the Zetafax server.

Return Value

[out, retval]

The Letterheads collection.

104

See Also Letterheads, Letterhead



Property Links As ZfLib.Links

The Links property returns a Links collection with information about the current state of the LCR links maintianed by the Zetafax server.

Return Value

[out, retval]

The Links collection.

See Also Links



equisys

ΓΑ/ΑΧ°



Property MaxDevices As Short

The MaxDevices property retrieves the maximum number of devices the Zetafax server supports.

Return Value

[out, retval]

The maximum number of devices allowed

Remarks

This property always returns 100.





Property MaxLinks As Short

The MaxLinks property retrieves the maximum number of LCR links the Zetafax server supports.

Return Value

ΤΑ/ΑΧ

[out, retval]

The maximum number of Remote Server links allowed



Property RemoteAccept As Short

The RemoteAccept property retrieves the number of message items currently accepted for sending by remote servers.

Return Value

[out, retval]

The number of items accepted by remote server.



equisys



Property RouterSub As Short

The RouterSub property retrieves the number of items submitted to the Router for sending and awaiting acceptance by a remote server.

Return Value

[out, retval]

This is the number of items submitted to Router





Property Scanning As Short

The Scanning property retrieves the number of items in the queue being processed by a scanning device.

Return Value

106

Zetafax 2012 API Help

[out, retval]

The numbers of scan request items in queue.





Property Sending As Short

The Sending property returns the number of items in the queue which are currently being sent.

Return Value

[out, retval]

The number of message items in the queue being sent.





Property WaitingConvert As Short

The WaitingConvert property retrieves the number of items in the queue waiting to be converted or being prepared for sending.

Return Value

[out, retval]

This is the number of items waiting to be converted.



ZfLib.ServerInfo.WaitingDevice

Property WaitingDevice As Short

The WaitingDevice property retrieves the number of items waiting for a device to become available.

Return Value

[out, retval]

The number of items awaiting device.





Property WaitingResend As Short

The WaitingResend property retrieves the number of items in the queue waiting before retrying after a send attempt failed.

Return Value

[out, retval]

The number of message items awaiting resend.



ZfLib.UserSession

The UserSession object contains details about a Zetafax user's configuration, messages and gives you the ability to create new messages for sending.

Groups

Operations

Read-only Properties

PIPrint <u>APIPrint</u>	The <u>APIPrint</u> property returns the APIPrint object
<u> </u>	The <u>Coversheet</u> property returns the user's default Coversheet .
PromName	The <u>FromName</u> property specifies the name of the logged on user as it appears in the from field of new messages.
^{Inbox}	The <u>Inbox</u> property returns the Inbox object.
In the second s	The <u>Outbox</u> property returns the <u>Outbox</u> object

108 Zetafax 2012 API Help

[™] <u>Server</u>	The <u>Server</u> property returns the <u>Server</u> object.
	The <u>SystemArea</u> property returns the Zetafax System directory.
[™] UserArea	The <u>UserArea</u> property returns path to the logged on Zetafax
⊠ [•] <u>UserInDir</u>	user's directory. The <u>UserInDir</u> property returns the User's IN directory.
Interest State St	The <u>UserOutDir</u> property returns the User's OUT directory.

See Also NewMessage , Inbox , Outbox





Property APIPrint As ZfLib.APIPrint

The APIPrint property returns the APIPrint object

Return Value

[out, retval]

An APIPrint object.

See Also APIPrint





Property Coversheet As String

The Coversheet property returns the user's default Coversheet.

Return Value

[out, retval]

The user's default Coversheet.




Function CreateNewMsg() As ZfLib.NewMessage

The CreateNewMsg method creates a <u>NewMessage</u> object.

Return Value

The new <u>NewMessage</u> object.

See Also NewMessage



equisys

ΖΕΤΑ/ΑΧ



Property FromName As String

The FromName property specifies the name of the logged on user as it appears in the from field of new messages.

Return Value

[out, retval]

The user's FromName.



Property Inbox As ZfLib.Inbox

The Inbox property returns the Inbox object.

Return Value

[out, retval]

An Inbox object.

See Also Inbox



Sub Logoff()

Logs of the user logged on in ZfAPI.Logon

Remarks

Note: This function will also be called during the object's destruction. It is primarily intended for occassions when you don't know when the object will be released.



equisys

ZÉTA/AX



Property Outbox As ZfLib.Outbox

The Outbox property returns the Outbox object

Return Value

[out, retval]

A Outbox object.

See Also Outbox





ZfLib.UserSession.SendSubmitFile

Function SendSubmitFile(ByVal bszSubFile As String, ByVal bszPrefix As String) As String

This method interpretes the given SUBMIT format file, creating a CONTROL file and a DATA file in ASCII text or EPSON print format. It then submits these files for sending.

Parameters

bszSubFile The name of the submit file

bszPrefix Prefix to use when creating control and data files

Return Value

The name of message body if successfully submitted.

See Also NewMessage



Property Server As ZfLib .Server

The Server property returns the Server object.

Return Value

[out, retval]

The Server object.

See Also Server



equisys

ΖΕΤΑΤΑΧ



Property SystemArea As String

The SystemArea property returns the Zetafax System directory.

Return Value

[out, retval]

The path of the Zetafax system directory.





Property UserArea As String

The UserArea property returns path to the logged on Zetafax user's directory.

Return Value

[out, retval]

The path to the User's area



Property UserInDir As String

The UserInDir property returns the User's IN directory.

Return Value

[out, retval]

The path of the User's IN directory.



equisys

Ζέτα/ΑΧ



Property UserOutDir As String

The UserOutDir property returns the User's OUT directory.

Return Value

[out, retval]

The path to the User's OUT directory.





The ZfAPI object is the Application object of the COM version of the API, and is the only object that can be created directly. You must create this object and logon before you can access any of the other objects.

Groups Operations

 GetZetafaxServerInfoFromAD GetZetafaxServersFromAD Logon LogonAnonymous SetZetafaxDirs SetZetafaxServerFromAD 	Gets Zetafax directories configured for the specified Zetafax server. Returns a list of Zetafax servers registered in Active Directory. The Logon method logs on a user and returns the UserSession object. The LogonAnonymous method returns a limited UserSession object that is not logged on as a specific user. Explicitly state the locations of the Zetafax directories instead of letting the API read zfclient. ini. Explicitly state the Zetafax server to use instead of letting the API read zfclient.ini.
Read-only Properties	
Provide the second seco	Gets the path to the Request directory set by SetZetafaxDirs or SetZetafaxServerFromAD .
<u> ServerDir</u> ServerDir Serv	Gets the path to the Server directory set by SetZetafaxDirs or SetZetafaxServerFromAD .
	Gets the path to the System directory set by SetZetafaxDirs or SetZetafaxServerFromAD .
IsersDir UsersDir	Gets the path to the Users directory set by SetZetafaxDirs_or SetZetafaxServerFromAD
Image: Market State	The Version property returns the current version of ZfLib library
Paraget Server	Gets the server set by SetZetafaxServerFromAD





Sub GetZetafaxServerInfoFromAD(ByVal bszServerName As String, ByRef pbszServerDir As String, ByRef pbszSystemDir As String, ByRef pbszUsersDir As String, ByRef p bszRequestDir As String)

Gets Zetafax directories configured for the specified Zetafax server.

Parameters

bszServerName The server name to look up in AD

CpbszServerDir The returned Server directory

CpbszSystemDir The returned System directory

CpbszUsersDir The returned Users directory CpbszRequestDir The returned Request directory

Return Value

If the directories have not been set by the Share Wizard, the method will return zfErrE_ACTIVE_DIRECTORY_MISSING_VALUE.

Remarks

This method queries Active Directory for the Zetafax server specified by bszServerName, and gets the directories that have been configured for the server by the Share Wizard.

See Also ZfAPI.GetZetafaxServersFromAD





Function GetZetafaxServersFromAD() As Variant

Returns a list of Zetafax servers registered in Active Directory.

Return Value

The returned server list

Remarks

This method queries Active Directory for installed Zetafax servers. It searches the Global Catalog if available, so will find any Zetafax servers installed in the forest.

See Also ZfAPI.SetZetafaxDirs , ZfAPI.GetZetafaxServerInfoFromAD





ZfLib.ZfAPI.Logon

Function Logon(ByVal bszUserName As String, ByVal fExclusive As Boolean) As ZfLib.UserSession

The Logon method logs on a user and returns the <u>UserSession</u> object.

Parameters

bszUserName The Zetafax User account

➡fExclusive

Exclusive Logon flag

Return Value

The returned UserSession object

Remarks

A successful call to this method is required to retrieve a UserSession object which allows access to all the other objects in ZfLib library. The method may be called more than once by the program if it wishes to logon more than one user. The fExclusive Boolean flag is set to FALSE if the specified user is permitted to be logged on elsewhere (either on a normal Zetafax client, or in another API program).

See Also

ZfAPI.LogonAnonymous, UserSession, UserSession.Logoff





Function LogonAnonymous() As ZfLib.UserSession

The LogonAnonymous method returns a limited UserSession object that is not logged on as a specific user.

Return Value

The returned UserSession object Remarks An anonymous session is restricted to the following methods in the UserSession object: UserSession.Server UserSession.SystemArea UserSession.Logoff All other methods return an error. See Also ZfAPI.Logon , UserSession , UserSession.Logoff





Property RequestDir As String

Gets the path to the Request directory set by <u>SetZetafaxDirs</u> or <u>SetZetafaxServerFromAD</u>.

Return Value

[out, retval]

The returned Request directory

ZfLib.ZfAPI.ServerDir

Property ServerDir As String

Gets the path to the Server directory set by <u>SetZetafaxDirs</u> or <u>SetZetafaxServerFromAD</u>.

Return Value

[out, retval]

The returned Server directory



equisys

ΖΕΤΑ/ΑΧ



Sub SetZetafaxDirs(ByVal bszServerDir As String, ByVal bszSystemDir As String, ByVal bszUsersDir As String, ByVal bszRequestDir As String)

Explicitly state the locations of the Zetafax directories instead of letting the API read zfclient.ini.

Return Value

Returns E_FAIL if a session has already been created on this object.

Remarks

The API normally requires the Zetafax client to be installed and uses the zfclient.ini file to find the Zetafax server. In some cases the client may not be used so this method allows the caller to specify the location of the Zetafax server.

See Also ZfAPI.SetZetafaxServerFromAD





Sub SetZetafaxServerFromAD(ByVal bszServerName As String)

Explicitly state the Zetafax server to use instead of letting the API read zfclient.ini.

Parameters

bszServerName

Name of Zetafax server machine

Return Value

Returns E_FAIL if a session has already been created on this object.

Remarks

The API normally requires the Zetafax client to be installed and uses the zfclient.ini file to find the Zetafax server. In some cases the client may not be used so this method allows the caller to specify the Zetafax server. This method looks up the Zetafax server in Active Directory, and sets the Zetafax server directories on this object.

See Also ZfAPI.SetZetafaxDirs





Property SystemDir As String

Gets the path to the System directory set by $\underline{\mathsf{SetZetafaxDirs}}$ or $\underline{\mathsf{SetZetafaxServerFromAD}}$.

Return Value

[out, retval]

The returned System directory





Property UsersDir As String

Gets the path to the Users directory set by <u>SetZetafaxDirs</u> or <u>SetZetafaxServerFromAD</u>.

Return Value

[out, retval]

The returned Users directory

ZfLib.ZfAPI.Version

Property Version As String

The Version property returns the current version of **ZfLib** library

Return Value

[out, retval]

The current ZfLib Version.

Remarks

API version





Property ZetafaxServer As String

Gets the server set by <u>SetZetafaxServerFromAD</u>

Return Value

[out, retval]

Returned server name

Remarks

Gets the server set by <u>SetZetafaxServerFromAD</u>





This is a list of the objects and enumerations that appear in the Zetafax COM library **Groups**

COM Classes

The API Print

This object allows the API to print via the Zetafax Printer.

The second second	The <u>Attachment</u> object
Attachment	contains the name of a
	Zetafax attachment to be
	attached to a message before
	it is sent.
	The <u>Attachments</u> collection
Attachments	object contains <u>Attachment</u>
	objects. The <u>Coversheet</u> class
Coversheet	represents a Zetafax
	coversheet.
Coversheets	The <u>Coversheets</u> collection
	object contains <u>Coversheet</u>
	objects.
Device	The <u>Device</u> object contains
	the configuration information
	and status of a device
	attached to the Zetafax
	server.
Devices	The <u>Devices</u> collection
	contains Device objects.
File	The File object contains the
	path of a file to be attached
	to the message before it is
	sent.
Files	The Files collection object
<u></u>	contains <u>File</u> objects. To
	attach Zetafax attachments
	to the message use the
	Attachments collection.
Tinbox	The Inbox object represents
	a user's Zetafax IN directory.
Letterhead	The <u>Letterhead</u> class
	represents a Zetafax
	letterhead.
Letterheads	The Letterheads collection
Ecternedus	object contains Letterhead
	objects.
Link	The Link object allows a user
	to retrieve information on the
	status of a link. It also
	provides statistics on the Link
	's performance.
Links	The Links collection contains
	Link objects.
Massage	The <u>Message</u> object allows
••••••••••••••••••••••••••••••••••••••	access to the details of sent
	and received messages.
HessageHistories	The MsgHistories collection
	represents a message's
	transmission history and
	contains MessageHistory
	objects.
	The MessageHistory object
MessageHistory	contains an item in a
	message's transmission
	history.
	The MessageInfo object
MessageInfo	contains information about a
	single Message object
• <mark>•••</mark> <u>Messages</u>	The <u>Messages</u> collection
messages	contains Message objects
	from either a User's Inbox or
	Outbox .
	The <u>NewMessage</u> object
	allows the logged on user to
	prepare and submit a new

Cutbox	message to the Zetafax server for sending. The <u>Outbox</u> object represents a user's Zetafax
Recipient	OUT directory. The <u>Recipient</u> object contains address details of an addressee for whom a
Recipients	message is intended. The <u>Recipients</u> collection object contains Recipient
Server Server	objects. The <u>Server</u> object allows control over the Zetafax
ServerInfo	server, and access to objects describing the server's state. The <u>ServerInfo</u> object exposes the status and configuration of the Zetafax server.
UserSession	The <u>UserSession</u> object

Contains details about a Zetafax user's configuration, messages and gives you the ability to create new messages for sending. The ZfAPI object is the Application object of the COM version of the API, and is the only object that can be created directly. You must create this object and logon before you can access any of the other objects.

Type Definitions

DevStatusEnum	The <u>DevStatusEnum</u> enumeration specifies the current status of a Device.
EventEnum	The <u>EventEnum</u> enumeration specifies the event described in a <u>MessageHistory</u> object
FaxTypeEnum	The <u>FaxTypeEnum</u> enumeration specifies how a recipient will be sent a message
FormatEnum	The FormatEnum enumeration specifies the format of the data file to be sent
HeaderEnum	This <u>HeaderEnum</u> Enumeration specifies the content of the header line to appear in the top
P LinkStatusEnum	page of each fax The <u>LinkStatusEnum</u> enumeration specifies the current status of an LCR link
PriorityEnum	The <u>PriorityEnum</u> enumeration specifies the priority of an
P <u>QualityEnum</u>	outgoing message The <u>QualityEnum</u> enumeration specifies the resolution when sending a fax







Enum ZfLib.DevStatusEnum

```
zfDevStatusIdle = 1
zfDevStatusError = 2
zfDevStatusFailed= 3
zfDevStatusOffline = 4
zfDevStatusBusy = 5
zfDevStatusWaitingConnect = 6
zfDevStatusSending = 7
zfDevStatusReceiving= 8
zfDevStatusWaitingScanDoc = 11
zfDevStatusIncomingCall= 13
```

End Enum

The DevStatusEnum enumeration specifies the current status of a Device.

Members

zfDevStatusBusy The device is busy processing a message

zfDevStatusError Trying to recover from an error

zfDevStatusFailed Unable to recover from error

zfDevStatusIdle The device is idle

zfDevStatusIncomingCall The device has receive a request to recieve data

zfDevStatusOffline The device has been turned off

zfDevStatusReceiving

Zetafax 2012 API Help

Recieving data

zfDevStatusSending Sending data

zfDevStatusWaitingConnect The device is attempting to connect to a remote device

zfDevStatusWaitingScanDoc Waiting for document to scan

See Also Device





Enum ZfLib.EventEnum

zfEventSentOK = 1 zfEventRecdOK = 2 zfEventScanOK = 3 zfEventSentError = 4 zfEventRecdError = 5 zfEventScanError = 6 zfEventTried = 7 zfEventRouterSub = 8 zfEventRouterAcc = 9 zfEventRouterErr = 10

End Enum

The EventEnum enumeration specifies the event described in a MessageHistory object

Members

zfEventRecdError Received with errors

zfEventRecdOK Received successfully

zfEventRouterAcc Accepted for transmission by remote server

zfEventRouterErr Submission to a remote server failed

zfEventRouterSub Passed to remote Zetafax server for sending

zfEventScanError Scanning request completed with errors

zfEventScanOK Scanned successfully zfEventSentError Sent with errors

zfEventSentOK Sent successfully

zfEventTried Send attempt was unsuccessful

See Also MessageHistory





Enum ZfLib.FaxTypeEnum

zfFaxTypeFax = 1 zfFaxTypeLAN = 2 zfFaxTypeSMS = 3

End Enum

The FaxTypeEnum enumeration specifies how a recipient will be sent a message

Members

zfFaxTypeFax Via fax

zfFaxTypeLAN Via LAN (used to send messages to another Zetafax User)

zfFaxTypeSMS Via SMS

See Also Recipient





Enum ZfLib.FormatEnum

```
zfFormatASCII= 1
zfFormatEpson= 2
zfFormatTIFFNormal = 3
zfFormatTIFFFine= 4
```

End Enum

The FormatEnum enumeration specifies the format of the data file to be sent

Members

zfFormatASCII ASCII text (TXT)

zfFormatEpson Epson FX or LQ print spool file (EPN)

zfFormatTIFFFine 200x200 dpi TIFF fax file (G3F)

zfFormatTIFFNormal 200x100 dpi TIFF fax file (G3N)

See Also NewMessage





Enum ZfLib.HeaderEnum

```
zfHeaderNone= 0
zfHeaderNumber = 1
zfHeaderTo = 2
zfHeaderFrom= 4
zfHeaderDate= 8
zfHeaderTime= 16
```

End Enum

This HeaderEnum Enumeration specifies the content of the header line to appear in the top page of each fax

Members

zfHeaderDate Show date

zfHeaderFrom Show name of sender

zfHeaderNone Turn all header information off

zfHeaderNumber Show page numbers

zfHeaderTime Show time

zfHeaderTo Show name of recipient Remarks The members of this enumeration can be ORed together

See Also <u>NewMessage.Header</u>





Enum ZfLib.LinkStatusEnum
zfLinkOnline = 1
zfLinkOffline= 2
zfLinkFailedWDog= 3
zfLinkInitialising = 4
zfLinkShutdown = 5
zfLinkUnknownState = 6
End Enum

The LinkStatusEnum enumeration specifies the current status of an LCR link

Members

zfLinkFailedWDog The server failed to receive an expected status message

zfLinkInitialising The link is initialising but has started communicating with the remote server

zfLinkOffline The remote server has closed the link or the local link is temporarily closed

zfLinkOnline The link functioning normally

zfLinkShutdown The link has been permanently closed.

zfLinkUnknownState The link is initialising and has not yet heard from the remote server

See Also Link





Enum ZfLib.PriorityEnum
zfPriorityBackground = 1
zfPriorityNormal = 2
zfPriorityUrgent = 3

Zetafax 2012 API Help

End Enum

The PriorityEnum enumeration specifies the priority of an outgoing message

Members

zfPriorityBackground Send at low priority

zfPriorityNormal Send with normal priority

zfPriorityUrgent Send urgently

See Also NewMessage





```
Enum ZfLib.QualityEnum
zfQualityHigh= 1
zfQualityNormal = 2
zfQualityDraft = 3
End Enum
```

The QualityEnum enumeration specifies the resolution when sending a fax

Members

zfQualityDraft Standard quality (200x100 dpi)

zfQualityHigh Fine quality (200x200 dpi)

zfQualityNormal Send the fax at default quality (configured by the Zetafax administrator)

See Also NewMessage





Enum ZfLib.RouteEnum
zfRouteFaxNormal = 2
zfRouteFaxFine= 3

zfRouteFaxSuperfine = 4 End Enum

The RouteEnum enumeration specifies the type of route used

Members

zfRouteFaxFine Fine resolution fax (200x200 dpi)

zfRouteFaxNormal Standard resolution fax (200x100 dpi)

zfRouteFaxSuperfine Super-fine resolution fax (200x400 dpi)

See Also MessageHistory





```
Enum ZfLib.SendTimeEnum
zfSendTimeNow = 1
zfSendTimeOffpeak = 2
zfSendTimeAfter= 3
End Enum
```

The SendTimeEnum enumeration specifies when a message will be sent

Members

zfSendTimeAfter Send after specified time

zfSendTimeNow Send as soon as possible

zfSendTimeOffpeak Send during offpeak rates

See Also NewMessage





Enum ZfLib.StatusEnum
zfStatusAdding = 1

```
zfStatusHeld = 2
zfStatusDeferred= 3
zfStatusWaiting = 4
zfStatusConverting = 6
zfStatusConnecting = 7
zfStatusSending = 8
zfStatusAborting= 10
zfStatusIncoming= 11
zfStatusSubRouter = 13
zfStatusAcceptRemote = 14
zfStatusOk= 30
zfStatusFailed = 31
zfStatusPreviewOK = 32
zfStatusPreviewFailed = 33
```

End Enum

The StatusEnum specifies the current status of a message

Members

zfStatusAborting The message is currently being aborted

zfStatusAcceptRemote Message accepted for transmission by remote server

zfStatusAdding Message added to the queue

zfStatusConnecting Connecting to remote device

zfStatusConverting Being prepared for sending

zfStatusDeferred Waiting for sending after a specific time

zfStatusFailed Completed with one or more errors

zfStatusHeld Message held by user

zfStatusIncoming Being received by a device

zfStatusOk Completed with no errors

zfStatusPreviewFailed Failed to prepare for preview

zfStatusPreviewOK Message ready for preview

zfStatusSending Sending to remote device

zfStatusSubRouter Passed to a remote Zetafax server for sending, but not yet acknowledged

zfStatusWaiting

Waiting for conversion or a free device to send the message

See Also MessageInfo





Enum ZfLib.UserStatusEnum zfUserStatusOK= 1 zfUserStatusAware= 2 zfUserStatusWaiting = 3 End Enum

The StatusEnum specifies the 'user status' of a message (that is the user's awareness of the message)

Members

zfUserStatusAware The user is aware of message, but has not read it.

zfUserStatusOK The message has been read.

zfUserStatusWaiting Waiting for user to do something.

See Also MessageInfo





```
Enum ZfErr
 zferre_INVALID_PARAM= &H8004F700
 zfErrE_NOT_INIT = &H8004F701
 zfErrE_INIT_FAIL = &H8004F702
 zfErrE_INVALID_ZF_INIT_FILE = &H8004F703
 zfErrE_INVALID_ZF_USER = &H8004F704
 zfErrE_CANNOT_LOG_ON= &H8004F705
 zfErre_CANT_LOG_ON = zfErre_CANNOT_LOG_ON
 zfErrE_PATH_NOT_FOUND = &H8004F706
 zfErrE_TOO_MANY_FILES = &H8004F707
 zfErre_FILE_CREATE_ERROR = &H8004F708
 zfErrE_FILE_OPEN_ERROR = &H8004F709
 zfErrE_FILE_ERROR= &H8004F70A
 zfErrE_FILE_NOT_FOUND = &H8004F70B
 zfErre_SERVER_NOT_RUNNING = &H8004F70C
 zferre_INVALID_DATA_FORMAT= &H8004F70D
```

Zetafax 2012 API Help

130

```
zfErrE_MSG_UNKNOWN = &H8004F70E
  zfErrE_MSG_NOT_COMPLETED = &H8004F70F
  zfErrE_MSG_EXISTS= &H8004F710
  zfErrE_INFO_FILE_OPEN_ERROR = &H8004F711
  zfErre_INFO_FILE_ERROR = &H8004F712
  zfErre_INFO_FILe_INVALID = &H8004F713
  zfErrE_CANNOT_SUBMIT= &H8004F714
  zferre_CANT_SUBMIT_REQUEST= zferre_CANNOT_SUBMIT
  zfErrE_BUFFER_TOO_SMALL= &H8004F715
  zfErre_SUBMIT_FILE_INVALID= &H8004F716
  zferre_CANNOT_READ_MSG_DEFAULTS = &H8004F717
  zferre_CANT_READ_MSG_DEFAULTS= zferre_CANNOT_READ_MSG_DEFAULTS
  zferre_CONTROL_FILe_OPEN_ERROR = &H8004F718
  zfErre_CONTROL_FILE_ERROR = &H8004F719
  zferre_CONTROL_FILE_INVALID = &H8004F71A
  zfErrE_SERVER_RUNNING = &H8004F71B
  zfErrE_NO_START_SYSMAN = &H8004F71C
  zferre_server_ini_file_error = &H8004F71e
  zfErrE_FUNCTION_ABORT = &H8004F71F
  zfErre_TIMEOUT_EXPIRED = &H8004F720
  zfErrE_MALLOC_FAILED= &H8004F724
  zfErrE_LICENCE_ERROR= &H8004F725
  zfErre_API_LICENSE_ERROR = &H8004F726
  zfErrE_USER_NOT_INIT= &H8004F727
  zfErrE_ACCESSDENIED = &H8004F728
  zfErrE_REGISTRY_ERROR = &H8004F729
  zferre_ACTIVE_DIRECTORY_NOT_PRESENT= &H8004F72A
  zfErrE_ACTIVE_DIRECTORY_ERROR= &H8004F72B
  zferre_ACTIVe_DIRECTORY_MISSING_VALUE = &H8004F72C
  zfErrE_FULLCOLLECTION = &H8004F730
End Enum
```

The ZfErr enumeration specifies the errors returned the API.

Members

zfErrE_ACCESSDENIED Access Denied

zfErrE_ACTIVE_DIRECTORY_ERROR Active Directory error

zfErrE_ACTIVE_DIRECTORY_MISSING_VALUE Active Directory value not set

zfErrE_ACTIVE_DIRECTORY_NOT_PRESENT Active Directory server not present

zfErrE_API_LICENSE_ERROR Your Zetafax licence does not permit you to use the API

zfErrE_BUFFER_TOO_SMALL The buffer in which to return data was too small

zfErrE_CANNOT_LOG_ON The user was already logged on or the API cannot access their directories

zfErrE_CANNOT_READ_MSG_DEFAULTS Cannot read user's USER.INI zfErrE_CANNOT_SUBMIT Error handling .SUB file

zfErrE_CONTROL_FILE_ERROR Error reading/writing CTL file

zfErrE_CONTROL_FILE_INVALID CTL file is corrupt

zfErrE_CONTROL_FILE_OPEN_ERROR The API was unable to open the message's CTL file.

zfErrE_FILE_CREATE_ERROR Too many open files

zfErrE_FILE_ERROR Could not read/write to file

zfErrE_FILE_NOT_FOUND The file could not be found

zfErrE_FILE_OPEN_ERROR Could not open file

zfErrE_FULLCOLLECTION The collection is full

zfErrE_FUNCTION_ABORT The function failed because a user defined callback function returned "Abort and Stop" status

zfErrE_INFO_FILE_ERROR Error updating/accessing MSGDIR.CTL

zfErrE_INFO_FILE_INVALID MSGDIR.CTL is invalid

zfErrE_INFO_FILE_OPEN_ERROR Could not open MSGDIR.CTL

zfErrE_INIT_FAIL The API failed to initialise

zfErrE_INVALID_DATA_FORMAT The data file format specified is not recognised

zfErrE_INVALID_PARAM An invalid parameter was passed to the Zetafax API

zfErrE_INVALID_ZF_INIT_FILE The API had problems reading ZETAFAX.INI

zfErrE_INVALID_ZF_USER An attempt was made to log on to the API with an invalid user

zfErrE_LICENCE_ERROR The API Could not find the Zetafax licence

zfErrE_MALLOC_FAILED The API ran out of memory.

zfErrE_MSG_EXISTS This message already exists

zfErrE_MSG_NOT_COMPLETED An attempt was made to modify a message that wasn't completed

Zetafax 2012 API Help

zfErrE_MSG_UNKNOWN The specified message could not be found

zfErrE_NOT_INIT A call was made to the API when it had not been initialised with a call to ZfAPI.Logon

zfErrE_NO_START_SYSMAN The API could not launch SYSMAN.EXE

zfErrE_PATH_NOT_FOUND The API was passed an invalid path

zfErrE_REGISTRY_ERROR Registry Error

132

zfErrE_SERVER_INI_FILE_ERROR Problems accessing SETUP.INI

zfErrE_SERVER_NOT_RUNNING The Zetafax server isn't running

zfErrE_SERVER_RUNNING The Zetafax server is running

zfErrE_SUBMIT_FILE_INVALID One or more lines in the specified .SUB file were invalid

zfErrE_TIMEOUT_EXPIRED The specified function did not complete within the timeout period

zfErrE_TOO_MANY_FILES There are too many files in this directory

zfErrE_USER_NOT_INIT The API couldn't find the user of this session

Remarks

The error number may be returned as an IDispatch error. To see how these numbers map to the IDispatch errors and Zetafax's C API errors see the page $\frac{\text{Errors}}{\text{Errors}}$



Change History

This document details the change history of the COM API.

9.0.322.0

New Objects:

ZfLib.APIPrint - Enables API to print via Zetafax Printer

New Methods/Properties:

ZfLib.ZfAPI.SetZetafaxDirs - Enables API to override default logon server specified in the zfclient.ini file ZfLib.ZfAPI.SetZetafaxServerFromAD - Enables API to override default logon server specified in the zfclient.ini file ZfLib.ZfAPI.GetZetafaxServersFromAD - Gets list of Zetafax servers registered in Active Directory ZfLib.ZfAPI.GetZetafaxServerInfoFromAD - Gets server directory shares from Active Directory ZfLib.ZfAPI.SystemDir - Returns System directory set by call to SetZetafaxDirs or SetZetafaxServerFromAD ZfLib.ZfAPI.ServerDir - Returns Server directory set by call to SetZetafaxDirs or SetZetafaxServerFromAD

ZfLib.ZfAPI.UsersDir - Returns Users directory set by call to SetZetafaxDirs or SetZetafaxServerFromAD ZfLib.ZfAPI.RequestDir - Returns Request directory set by call to SetZetafaxDirs or SetZetafaxServerFromAD ZfLib.ZfAPI.ZetafaxServer - Returns Zetafax server set by call to SetZetafaxServerFromAD

Changes to Enumerations:

ZfLib .ZfErr - Added zfErrE_REGISTRY_ERROR, zfErrE_ACTIVE_DIRECTORY_NOT_PRESENT, zfErrE_ACTIVE_DIRECTORY_ERROR, zfErrE_ACTIVE_DIRECTORY_MISSING_VALUE

8.0.0.104

New Objects:

ZfLib.Coversheet - Holds the name of a coversheet ZfLib.Coversheets - Contains a collection of Coversheet objects ZfLib.Letterhead - Holds the name of a letterhead ZfLib.Letterheads - Contains a collection of Letterhead objects

New Methods/Properties:

ZfLib.Message.MarkMsgAsRead - This method marks a message as read ZfLib.MessageHistory.Name - Name of recipient associated with this MessageHistory item ZfLib.MessageHistory.Organisation - Organisation of recipient associated with this MessageHistory item ZfLib.MessageInfo.Organisation - Property containing the organisation of the first recipient of the message

ZfLib.MessageInfo.Type - Property containing the type of the Message (Fax, or SMS)

ZfLib.MessageInfo.UserStatus - Property containing the UserStatus of a message. Can be used to tell if the message has been read

ZfLib.NewMessage.Body - After the NewMessage.Send has been called this property contains the unique file body of the message

ZfLib.Recipients.AddSMSRecipient - This method adds an SMS recipient to the message ZfLib.ServerInfo.Coversheets - Property that returns a collection of Coversheets

Zetafax 2012 API Help

ZfLib.ServerInfo.Letterheads - Property that returns a collection of Letterheads ZfLib.UserSession.Logoff -Ends a session.

ZfLib.ZfAPI.LogonAnonymous - Creates an anonymous session

Changes to Enumerations:

ZfLib.UserStatusEnum - New enumeration used by MsgInfo.UserStatus ZfLib.FaxTypeEnum - Added zfFaxTypeSMS ZfLib .ZfErr - Added zfErrE_ACCESSDENIED and zfErrE_FULLCOLLECTION ZfLib.StatusEnum - Added zfStatusPreviewOK and zfStatusPreviewFailed

Behavioural Changes:

COM+ - If available, the COM API now runs using the security call context

Permissions - The COM API now checks access permissions before attempting file operations. If the required permissions are not available the call will fail with zfErrE_ACCESSDENIED

There have also been changes to improve general efficiency and speed of some of the COM API's properties and

methods



C language API

The C language Application Programmer's Interface (API) allows application programs to submit faxes to the Zetafax server for sending, and to control and monitor their progress as required.

A simple function call is provided to submit an ASCII text file in a given format. This format (termed Submit file format) includes details of the recipients of a message, in addition to the message text which can include text formatting such as bold and underlining. See <u>The ZSUBMIT program</u> for more on the Submit file format.

A range of other function calls allow other supported file formats to be submitted, and give full control over messages queued for a given user.

Libraries

The API comprises a set of C callable functions. It is distributed as a set of object libraries and a DLL (for use in different environments) for building into the application programs, together with a C header file containing definitions required to call the API functions. The following operating systems are currently supported:

- Microsoft Windows XP Professional
- Microsoft Windows Vista
- Microsoft Windows 7
- Microsoft Windows Server 2003
- Microsoft Windows Server 2008

Compilers

The object libraries for the API are available for use with the Microsoft C/C++ compiler.

File system structure

When the API is initialized you must specify a Zetafax username. Messages submitted by the API will appear as if submitted from a client logged on as this user, and the defaults for items such as the coversheet From name will be those for the user (exactly as if you submit a message from the client without changing any of the default values).

Store the message files to be sent in the user's out sub directory USERS\\username\Z-OUT, where username is the username. If necessary API programs can use the ZfxGetUserOutDir function to get the name of this directory.

A message for sending consists of two files in the out directory: a control file and a data file. Both of these files, and all other files created by the server relating to this message, have the name *filename.ext* where *filename* identifies the message, and *ext* identifies the type of file. The *filename* is referred to in the API as the message body name, and this is supplied to the API functions when specifying messages to submit, delete, etc. The ZfxCreateAutoFile function is used to create a file with a unique body name in a given directory.

The control file is identified with a .CTL extension. This is an ASCII text file and gives full details of the options to be used in preparing a message for sending, including the coversheet, letterhead, and priority, together with details of the intended recipients of the message (name, organization, fax number, etc.). The file is updated by the server as the message is processed to give details of the progress for each addressee, errors, etc. For use with the API this file will generally have been created by interpreting a Submit format file.

The data file contains the message to be sent, and its extension depends on the format of the data.

Supported formats are as follows:

Extension	Format
.TXT	ASCII text
.EPN	Epson FX or Epson LQ Windows driver
.G3NTIFF	fax format normal resolution (200x100 dpi)
.G3FTIFF	fax format fine resolution (200x200 dpi)

Message information

When a message is submitted to the server for sending (after creating a control file and a data file for the message), an entry is made in the info file in the user's out directory. This entry includes the file name of the message, the comment associated with it, and the current status of the message (converting, sending, etc.). The server is then notified that a new message is ready for sending, and will add the message to its queue.

The status field is updated by the server program as the message is processed. When the server completes processing of the message and the status has changed to OK or FAILED the message may be deleted. This is done by removing the info file entry then deleting the message files, and may be done either from the client or via the API.

Details of a message in the info file may be obtained using the ZfxGetMsgInfo or ZfxGetMsgList routines, giving details of a single message or all messages in the info file respectively. These store the information in a data structure of type ZFMSGINFO. The fields in this structure are as follows:

Field	Structure
szBody	Character string giving the body name of the message files (i.e. the file name without extension or preceding period.). The maximum length of this string (excluding terminating NULL) is given by the constant ZFMSG BODY LEN.
szComment	Character string giving the description of the message being sent (as displayed on the right in the client main display). The maximum length of this string (excluding terminating NULL) is given by the constant ZFMSG COMMENT LEN.
Status	Current status of message. This is a variable of type ZFMSGSTATUS, and the value is one of the ZFMSG_??? values listed below.

The following list gives the possible states for a message and their meanings:

State ZFMSG_ADDING ZFMSG_HELD	Meaning Message being added to queue. Message held by user.
ZFMSG_DEFERRED	Message waiting for sending after a specific time, either because that time was specified when the message was submitted, or the user does not have sufficient permissions to send until after the given time.
ZFMSG_WAITING	Waiting for conversion or for a free device to send the message.
ZFMSG_CONVERTING	Preparing the message for sending (merging with letterhead, creating coversheet, e.t.c.).
ZFMSG_CONNECTING	Dialing remote device, or connecting to local printer, etc.

136

ZFMSG_SENDING ZFMSG_SCANNING ZFMSG_ABORTING	Connection made, sending message to remote device. Not applicable. Processing an Abort request, waiting for device controller or convert program to cancel processing of the message. ZFMSG_INCOMING Being received by the device.
ZFMSG_OK	Completed (sent) successfully, with no errors. The message may now be deleted
ZFMSG_FAILED.	(using the ZfxDeleteMsg function). Completed with one or more errors. Details of the errors which occurred are listed in the control file, although this would normally be checked manually. The message may now be deleted (using the ZfxDeleteMsg function)

Related topics

<u>Function error returns and reference</u> <u>Alphabetical reference</u> <u>Message information functions</u> <u>Message transmission history functions</u> <u>Server and device status functions</u> <u>Converting from older versions of the API</u>



Converting programs from older versions of the Zetafax API

The API has been significantly extended over time. Existing API programs will continue to work correctly, and need not be rebuilt. However, any program which is to be rebuilt with the new version of the library will need some modification.

Version differences from versions 4.5 to 5 and 5 to 6 are detailed below.

For API 4.5 programs, a set of porting macros are included in the header file ZFAPI.H to allow programs to be ported with minimal changes (the addition of "#define" line before ZFAPI.H is included). They translate from the old function names to the new ones adding the necessary extra parameters. These are enabled by adding the following line before ZFAPI.H is included:

#define API_VER 0x450

For API 5 programs the superceded function names and structures are still supported by the DLLs and libraries, but by default are not included in the header file to assist new programmers. To continue using the old functions, add the following line before ZFAPI.H is included:

#define API_VER 0x500

However, the modifications required to reflect the changes described above are minor and quick to do. For clarity, it is therefore recommended that these changes are made in any programs which are still being developed or maintained, rather than relying on the porting macros.

Differences between version 4.5 and version 5

The API was significantly extended with Zetafax 5.

New features included:

- DLL version of library functions added
- Support for received faxes
- Retrieval of default user settings
- Support for multiple data files for each message
- Specifying the coversheet text in SUBMIT files

These enhancements made it necessary to make a number of changes to the original functions. The changes necessary for programs using version 4.5 are:

- 1. All functions have been renamed from Zf... to Zfx... (to ensure that any mismatching of old and new source code gives linker warnings).
- Previously a function named ZfPrintError had to be written and was called directly by the API libraries. This function can now have any name, and is passed as a parameter to ZfxAPIInit. The prototype of the function has now changed to: void ZFAPICALLBACK Proc(CHAR FAR *)
- 3. All functions other than ZfxAPIInit and ZfxGetAPIVersion now take a session handle (of type ZFSESSIONHANDLE) as the first parameter. This is returned in the first parameter by the ZfxAPIInit function.
- 4. The following functions have an extra parameter of type ZFMSGDIR, to specify whether the function should act on the OUT or IN directory: ZfxAbortMsg, ZfxHoldMsg, ZfxReleaseMsg, ZfxDeleteMsg, ZfxCheckNewMsgStatus, ZfxGetMsgInfo, ZfxGetMsgList, ZfxGetMsgHistory
- 5. ZfxGetAPIVersion has an additional parameter to return an integer value giving the version number. This can be NULL if not required.
- 6. The functions ZfSendSubmitFile, ZfCreateCtlFile and ZfCreateDataFile have been changed so they now take file names (CHAR FAR *) instead of file pointers (FILE *) to allow them to be used in the DLL version of the library. Three functions ZfxSendSubmitFileFP etc have been supplied in the static library version of the API to simplify porting of existing applications; these take file pointers as before.

Differences between version 5 and version 6

The API has been extended again for Zetafax 6.

New features include:

- Support for the subject line in faxes

- Inclusion of Least Cost Routing information in message status, message history, and server status

calls

- Info structures and functions extended

These enhancements made it necessary to add new some new functions to the API. The new functions are similar to the original functions, but include extra parameters for newly supported features.

The following structures are new, replacing the equivalent structures without the "EX" ending:

ZFMSGINFOEX ZFMSGHISTORYEX ZFSERVERINFOEX

The following functions are new, replacing the equivalent functions without the "Ex" ending:

ZfxGetServerStatusEx ZfxGetMsgHistoryEx ZfxGetMsgInfoEx ZfxGetMsgListEx

Related topics

Function error returns and reference Alphabetical reference Message information functions Message transmission history functions Server and device status functions



Function overview

This section gives a brief overview of the functions which comprise the API.

User supplied functions

If an API function encounters an error, it can call a user-supplied error routine with a textual error string before returning an error code to the calling program. This can be particularly useful when writing or testing the application.

General routines

Before using any API functions the program should call ZfxAPIInit. This specifies the username to use and returns a handle which is used in subsequent calls. It may be called more than once with different usernames if required. The ZfxAPIClosedown routine should be called by the program for each handle returned by ZfxAPIInit before exiting. The ZfxGetAPIVersion function returns the version number of the library (for printing in a startup message). ZfxCreateAutoFile generates a file in a given directory so that no other files exist with the same body name. Finally ZfxCheckServer checks whether the Zetafax server is running (although several of the other routines will also return an error if the Zetafax server is not running when they are called).

User information

Messages submitted by API programs use the Zetafax user's default settings for any message options which are not specified directly. The ZfxGetUserCoversheet and ZfxGetUserFromname functions return the user's default coversheet and sender name, and are used when a program wants to change its behavior depending on these settings.

Location of files

The standard Zetafax installation gives each user a base sub directory called USERS*username* where *username* is the username. Message files for sending and received messages are stored by the server in sub directories USERS*username*\Z-OUT and USERS*username*\\Z-IN respectively. The full pathnames of these directories are returned by the ZfxGetUserArea, ZfxGetUserOutDir and ZfxGetUserInDir functions respectively. Although not normally needed, the ZfxGetSystemArea routine may be used to obtain the full pathname of the SYSTEM sub directory, used for storing letterheads, etc.

Submitting a message

The simplest method of submitting a fax for sending is to create an ASCII text Submit file containing both the message options and the message text, then call the ZfxSendSubmitFile function. This creates a control and data file in the user's out directory, then submits the message to the server (which also makes an entry in the info file for that user).

Alternatively these three stages may be carried out independently. The ZfxCreateCtlFile function interprets the %%[MESSAGE] section of a Submit file, which contains details of the message options and addresses, and generates a control file. The ZfxCreateDataFile interprets the %%[TEXT] section of a Submit file to generate an ASCII text or Epson FX format data file if required (or a file of the correct format could simply be copied or created by the program). Finally the ZfxSendMsg function makes an entry in the info file and submits a control and data file pair to the server.

Programs which are unable to store a session handle for passing to the other routines can use ZfxVBSendSubmitFile. This is a self contained function which initializes an API session, submits a file, then closes the session again, and is ideal for calling from Visual Basic or macro languages.

There are three additional routines ZfxSendSubmitFileFP, ZfxCreateCtlFileFP and ZfxCreateDataFileFP which are provided to assist in porting programs written for older versions of the API. Their functions are the same as their namesakes above, but they use C file pointers instead of file names and are therefore

only supported in the static libraries, not in the DLL.

Server status

ZfxCheckServer checks whether the fax server is running (although several of the other routines will also return an error if the fax server is not running when they are called). ZfxGetServerStatusEx returns information about the server, including the number of queued messages in various states, the status of each of the devices, and the status of any links to remote servers.

Server control

ZfxStartServer, ZfxStopServer and ZfxRestartServer can be used to control the Zetafax server programs for completely automated systems.

Message control

Once a message has been submitted to the Zetafax server, its status may be obtained using the ZfxGetMsgInfo function. When the message completes, this function also specifies whether it was successfully transmitted. The ZfxGetMsgHistory function can be used to retrieve the full transmission history for the message, including details such as the number of dial attempts made and the connection time.

The ZfxGetMsgList function returns the status of all messages currently queued (or completed but not yet deleted) for the given user. The ZfxCheckNewMsgStatus function is used in conjunction with this - it checks whether the status of any messages for the user have changed since it was last called to save the overhead involved in calling ZfxGetMsgList unnecessarily.

The ZfxAbortMsg function requests the Zetafax server to abort processing of a given message (i.e. stop preparation or transmission of the message). When the server has completed processing it sets the message status to OK or FAILED. Messages in either of these states may be deleted from the info file by calling ZfxDeleteMsg. Optionally, this will also delete the control and data files for the message, together with any other temporary files generated by the server. The ZfxDeleteMsg function can also be used to delete all messages for a given user.

The ZfxHoldMsg and ZfxReleaseMsg functions can be used to pause and then resume processing for a specific message. Held messages are not submitted to devices for sending, though they retain their position in the queue.

These functions, except ZfxAbortMsg, ZfxHoldMsg, ZfxRushMsg and ZfxReleaseMsg, can also be used for received messages. API licensing

The API must be licensed on each Zetafax system on which you wish to run programs which use it (including the ZSUBMIT program). Call Equisys or your supplier for price details of multiple licenses.

Related topics

<u>Function error returns and reference</u> <u>Alphabetical reference</u> <u>Message information functions</u> <u>Message transmission history functions</u> <u>Server and device status functions</u> Converting from older versions of the API



Message information

When a message is submitted to the server for sending (after creating a CONTROL file and DATA file for the message), an entry is made in the INFO file in the user's OUT directory. This entry includes the file name of the message, the comment and subject line associated with it, and the current status of the message (converting, sending etc). The server is then notified that a new message is ready for sending, and will add the message to its queue.

The status field is updated by the server program as the message is processed. When the server completes processing of the message (and the status has changed to OK or FAILED) the message may be deleted. This is done by removing the INFO file entry, then deleting the message files, and may be done either from the client or via the API.

Details of a message in the INFO file may be obtained using the ZfxGetMsgInfoEx or ZfxGetMsgListEx routines, giving details of a single message or all messages in the INFO file respectively. These store the information in a data structure of type ZFMSGINFOEX. The fields in this structure are as follows.

Field Status	Description Current status of message. This is a variable of type ZFMSGSTATUS, and the value is one of the ZFMSG_??? values listed below. <u>Message status</u> variables are given
szBody	below. Character string giving the body name of the message files (ie the file name without extension or preceding '.'). The maximum length of this string (excluding terminating NULL) is given by the
szComment	constant ZFMSG_BODY_LEN. Character string giving the description of the message being sent (as displayed on the right in the client main display). The maximum length of this string (excluding terminating NULL) is
szSubject	given by the constant ZFMSG_COMMENT_LEN. Character string giving the subject of the message being sent (as displayed on the right in the client main display). The maximum length of this string (excluding
UserStatus	terminating NULL) is given by the constant ZFMSG_SUBJECT_LEN. Current status of message in relation to the user. This is a variable of type ZFMSGUSERSTATUS, and the value is one of the ZFMSG_??? values
Туре	listed below. <u>User status</u> variables are given below. Type of message. This is a variable of type ZFMSGTYPE, and the value is one of the ZFTYPE_??? values listed below. <u>Type</u> variables are
szOrganisation	given below. Character string giving the

organisation field for the message being sent. The maximum length of this string (excluding terminating NULL) is given by the constant ZFMSG_COMMENT_LEN.

Message status

The following list gives the possible states for a message (variable of type ZFMSGSTATUS).

Message state ZFMSG_ADDING ZFMSG_HELD ZFMSG_DEFERRED	Description Message being added to queue Message held by user Message waiting for sending after a specific time, either because that time was specified when the message was submitted, or the user does not have sufficient permissions to send until after the given time.
ZFMSG_WAITING	Waiting for conversion or for a free device to send the
ZFMSG_CONVERTING	message. Preparing the message for sending (merging with letterhead,
ZFMSG CONNECTING	creating coversheet etc). Dialling remote device, or
_	connecting to local printer etc.
ZFMSG_SENDING	Connection made, sending message to remote device.
ZFMSG_SUB_ROUTER	Passed to a remote Zetafax server for sending, but not yet
ZFMSG_ACCEPT_REMOTE	acknowledged. Message accepted for transmission by a remote
ZFMSG_SCANNING ZFMSG_ABORTING	Zetafax server. (not applicable) Processing an Abort request, waiting for device controller or
ZFMSG_INCOMING ZFMSG_WAITING_SCAN_DOC ZFMSG_OK	convert program to cancel processing of the message. Being received by the device. (not applicable) Completed (sent or received) successfully, with no errors. For sent messages the message may
ZFMSG_FAILED	now be deleted (using the ZfxDeleteMsg function). For received messages the DATA file contains the received message, so should be saved (if required) before calling ZfxDeleteMsg. Completed with one or more errors. Details of the errors that occurred are listed in the CONTROL file, although this would normally be checked manually. The message may now be deleted (using the ZfxDeleteMsg function). For received faxes any part of the message received before the error occurred will still be stored
ZFMSG PREVIEW OK ZFMSG PREVIEW FAILED	in the DATA file. (not applicable) (not applicable)

User status

The following list gives the possible users states for a message (variable of type ZFMSGSTATUS).

Message state ZFMSG_U_UNKNOWN ZFMSG_U_OK ZFMSG_U_AWAITING ZFMSG_U_WAITING **Description** User Status unknown. Message has been read by user. Message awaiting preview. Waiting - i.e. unread.

User status

The following list gives the possible values for the message type field (variable of type ZFMSGTYPE).

TypeDescriptionZFTYPE_FAXFax message.ZFTYPE_LANMessage for another Zetafax user
(on the same LAN).ZFTYPE_SMSText message.

1 top

Related topics <u>Function overview</u> <u>Function error returns and reference</u> <u>Alphabetical reference</u> <u>Message transmission history functions</u> <u>Server and device status functions</u> <u>Converting from older versions of the API</u>
equisys ZETA/AX[®]

Message transmission history

Details of the transmission history for a message in the CONTROL file may be obtained using the ZfxGetMsgHistoryEx routine, giving details of a single addressee or all addressees. This stores the information in a data structure of type ZFMSGHISTORYEX. The fields in this structure are as follows:

Below you will find details for: Message transmission history

transmission history	<u>Message event types</u>	<u>Message routes</u>

Message transmission history

Field EventType	Description Type of this record. This is a variable of type ZFMSGEVENT, and the value is one of the ZFEVENT_??? values listed below.
Year Month Day Hours Mins Secs AddrNum	Event timestamp (range 1980 to 2079) Event timestamp (range 1 to 12) Event timestamp (range 1 to 31) Event timestamp (range 0 to 23) Event timestamp (range 0 to 59) Event timestamp (range 0 to 59) Addressee number (starts from 1). When a single message has been addressed to more than one person, this
Route	allows the events to be identified. Route type used. This is a variable of type ZFMSGROUTE, and the value is one of the ZFROUTE_??? values listed below.
szRouteParams	Route parameters used. For fax routes this is the fax number dialled. The maximum length of this string (excluding terminating NULL) is given by the
ErrorCode	constant ZFDEV_PARAMS_LEN. Reason for failure. This is a variable of type ZFERR. The error code can be any of the L2ERR_??? values given in the file ZFERR.H - however note that the values depend on the version of the Zetafax server running, not the version of the API used. New versions of the server
PagesSent	will have additional error codes. Number of last page successfully sent (including the coversheet if used). If a three page message had several attempts at sending, but only the first two pages were sent successfully, this value would be set to 2. For event type ZFEVENT_SENT_OK this is the total
ConnectSecs	number of pages in the message. Connection time in seconds. This field only applies to events of type ZFEVENT_SENT_OK and ZFEVENT_SENT_ERROR, and gives the total connect time for the given
szDevice	addressee. The name of the device used to send the message. The maximum length of this string (excluding terminating NULL) is

given by the constant ZFDEV_NAME_LEN. szRemoteServer The name of the remote server used to send the message via LCR. The maximum length of this string (excluding terminating NULL) is given by the constant ZFDEV_NAME_LEN.

1 top

Message event types

The following list gives the possible event types for a message (variable of type ZFMSGEVENT).

Event ZFEVENT_SENT_OK ZFEVENT_RECD_OK ZFEVENT_SCAN_OK ZFEVENT_SENT_ERROR	Description Sent successfully Received successfully Scanned successfully Sent with errors - the connection time and number of pages can be used to determine whether the error was during connection or transmission
ZFEVENT_RECD_ERROR ZFEVENT_SCAN_ERROR	Received with errors. Scanning request completed with
ZFEVENT_TRIED	errors. Send attempt unsuccessful. The Zetafax server makes several attempts to send to a given addressee. This event is logged if a send attempt is unsuccessful, but the server will retry later. If all attempts are unsuccessful, the last attempt will be logged as an event of type ZFEVENT_SENT_ERROR, while all previous events are logged as ZFEVENT TRIED events.
ZFEVENT_ROUTER_SUB	Passed to remote Zetafax server for sending (when Least Cost
ZFEVENT_ROUTER_ACC	Routing in use) Accepted for transmission by remote server
ZFEVENT_ROUTER_ERR	Submission to a remote server failed

1 top

Message routes

The following list gives the possible routes for fax messages (variable of type ZFMSGROUTE). Note that other routes are also supported by the Zetafax server, so this list is not exhaustive.

Route	Description
ZFROUTE_FAX_NORMAL	Standard resolution fax (200 x 100 dpi)
ZFROUTE_FAX_FINE	Fine resolution fax (200 x 200 dpi)

1 top

Related topics Function overview Function error returns and reference

C language	API	147
------------	-----	-----

Alphabetical reference Message information functions Server and device status functions Converting from older versions of the API



Message defaults

This structure conatins the default message settings for the user. It is used in the ${\tt ZfxGetMsgDefaultsEx()}$ function

Field PriorityDefault priority.	Description This is a variable of type ZFMSGPRIORITY, and the value is one of the ZFPRIORITY_??? values listed below. <u>Priority</u> variables are given below.
HeaderDefault header.	This is a variable of type ZFMSGHEADER, and can be a combination of one or more of the ZFHEADER_??? values listed below. <u>Header</u> variables are given below. These values should be combined using the bitwise-OR operator
QualityDefault Quality.	This is a variable of type ZFMSGQUALITY, and the value is one of the ZFQUALITY?? values listed below. <u>Quality</u> variables are given below.
SendTime	Variable of type ZFSENDTIME determining when a message submitted by the user will be sent. The value is one of the ZFSENDTIME??? values listed below. <u>Send Time</u> variables are given below.
AfterYear, AfterMonth, AfterDay, AfterHour, AfterMin, AfterSec;	Short integer values specifying the 'send after' time. These parameters are
szFrom	Character string giving the from field to use. The maximum length of this string (excluding terminating NULL) is given by the constant ZFMSG_FULLNAME_LEN.
szCoversheet	Character string giving the name of the coversheet to use. The maximum length of this string (excluding terminating NULL) is given by the constant ZFMSG_COVERSHEET_LEN.
szLetterhead	Character string giving the name of the letterhead to use. The maximum length of this string (excluding terminating NULL) is given by the constant ZFMSG_LETTERHEAD_LEN.

Priority

The following list gives the possible values for message priority.

Message priority	Description
ZFPRIORITY_BACKGROUND	The lowest priority - messages with this priority will be processed after
	messages with other priorities.
ZFPRIORITY_NORMAL	Standard priority
ZFPRIORITY_URGENT	The highest priority - messages with this priority will take precedance over messages with other priorities.

Message header

The following list gives the possible message header settings (variable of type ZFMSGHEADER).

Message header setting

ZFHEADER_NONE ZFHEADER_NUMBER ZFHEADER_TO ZFHEADER_FROM ZFHEADER_DATE ZFHEADER_TIME

Description

No setting. Phone number. To field. From field. Date field. Time field.

Quality

The following list gives the possible values for message quality.

Message quality ZFQUALITY_DRAFT ZFQUALITY_NORMAL ZFQUALITY_HIGH

Send time

The following list gives the possible values for the SendTime field.

Send time

ZFSENDTIME_NOW ZFSENDTIME_OFFPEAK ZFSENDTIME_AFTER

Description

Low quality. Standard quality. High quality.

Description

Send the message immediately. Send the message during the offpeak period. Send the message after the time specified by the 'send after' fields.

1 top

Related topics <u>Function overview</u> <u>Function error returns and reference</u> <u>Alphabetical reference</u> <u>Message transmission history functions</u> <u>Server and device status functions</u> <u>Converting from older versions of the API</u>

Server and device status

Details of the status of the server and the configured devices and links may be obtained using the ZfxGetServerStatusEx function. It is passed a structure of type ZFSERVERSTATUSEX which defines what information is required. The structure includes the addresses of three further structures of type ZFSERVERINFOEX, ZFDEVICEINFOEX and ZFLINKINFOEX, which are used to return the information.

Below you will find information on:

Server informationServer statusDevice informationDevice statusLink informationLink status

Server status

Field ServerInfoExSize IpServerInfoEx	Description Should be set to sizeof (ZFSERVERINFOEX) Address of a SERVERINFOEX structure, to be filled on return
MaxDevices	Maximum number of device entries to be returned (i.e. number of elements in the
lpNumDevices	DeviceInfo array) Address of short integer variable used to return the number of devices in the file. Note: that the returned value may be larger than the value given for MaxDevices if the buffer was not large enough for all entries.
DeviceInfoEx	Size Should be set to sizeof
IpDeviceInfoEx	(ZFDEVICEINFOEX) Address of array of 'n' ZFDEVICEINFOEX structures, where 'n' is the value given by the MaxDevices parameter.
MaxLinks	Maximum number of LCR link entries to be returned (ie number of elements in the LinkInfoEx array)
lpNumLinks	Address of short integer variable used to return the number of links in the file. Note that the returned value may be larger than the value given for MaxLinks if the buffer was not large enough for all entries.
LinkInfoExSize	Should be set to sizeof
lpLinkInfoEx	(ZFLINKINFOEX) Address of array of 'n' ZFLINKINFOEX structures, where 'n' is the value given by the MaxLinks parameter.

1 top

equisys ZETA/AX[®]

Server information

The fields in the ZFSERVERINFOEX structure are as follows:

Field Queue	Description Deferred Number of items in queue waiting until a given time (excluding those waiting before retrying after
QueueWaitingResend	failure). Number of items in queue waiting before retrying after
QueueWaitingConvert	a send attempt has failed. Number of items in queue waiting to be converted
QueueConverting	(prepared for sending). Number of items in queue being converted (prepared for sending) - currently either 0 or 1.
QueueWaitingDevice	Number of items in queue waiting for a device to become available
QueueSending	Number of send requests in queue being processed by a device - either connecting or sending.
QueueScanning	Number of scan requests items in queue being processed by a scanning device.
QueueSubRouter	Number of items submitted to Router for sending, and awaiting acceptance by a
QueueAcceptRemote	remote server. Number of items currently accepted for sending by remote servers

1 top

Device information

The fields in the ZFDEVICEINFOEX structure are as follows:

Field szDevice	Description Name of the device. Device names comprise a device type and device number, separated by a hyphen (eg "FCLASS-3"). Two devices of different types can have the same number. The maximum length of this string (excluding terminating
Status	NULL) is given by the constant ZFDEV_NAME_LEN. Current status of the device. This is a variable of ZFDEVSTATUS, and the value is one of the
szUser	ZFDEV_??? values listed below. User name of owner of message currently being processed by the device (or

	null string if no message being processed). The maximum length of this string (excluding terminating NULL) is given by the constant
szMsgBody	ZFUSER_NAME_LEN. Body name of message CONTROL file currently
	being processed by the device (or null string if no message being processed).
NumPages	Number of pages in message currently being processed (including
CurrentPage	coversheet if used) Page number currently being sent.
NumConnect Fails	Number of send attempts by this device which have failed to connect.
NumSendFails	Number of send attempts by this device which have
NumSentOK	failed after connection. Number of messages sent successfully by the device.

Device status

The following list gives the possible status values for a device (variable of type ZFDEVSTATUS).

Field ZFDEV_UNKNOWN_STATE	Description Status unknown (eg not initialized yet). This could also occur if an API program is run with a later version of the Zetafax server which
ZFDEV_IDLE ZFDEV_ERROR ZFDEV_FAILED	supports additional device states. Ready for sending Trying to recover from error Unable to recover from error. The device status changes to ZFDEV_FAILED when the device is unable to recover from a status of ZFDEV ERROR (generally after a
	fixed period of time).
ZFDEV_OFFLINE	Device set offline by user, and unavailable for sending
ZFDEV_BUSY	Generally busy, and unavailable for
ZFDEV_WAITING_CONNECT	sending Waiting for connection (for fax messages, this is the status between dialing the fax number and completing the fax handshake). Note that for dialed calls, the connection time starts from when the modem reports that the remote device has answered the call - the device status will generally be ZFDEV_WAITING_CONNECT for several seconds after this.
ZFDEV_SENDING	Connected to the remote device
ZFDEV RECEIVING ZFDEV POLL SEND ZFDEV POLL RECEIVE ZFDEV_WAITING_SCAN_ DOC	and sending the message. Receiving an incoming message Not supported Not supported For scanning requests, waiting for

1 top

ZFDEV_SCANNING ZFDEV_INCOMING_CALL the document to be scanned to be placed on the device. Not supported Answering an incoming call - state will change to ZFDEV_RECEIVING once the correct handshaking has occurred

1 top

153

Link information

The fields in the ZFLINKINFOEX structure are as follows:

Field szRemoteServer	Description Name of the remote server to which the link is configured. The maximum length of this string (excluding terminating NULL) is given by the constant
RemoteLinkStatus	ZFDEV_NAME_LEN. Current status of the remote server on the link. This is a variable of type ZFLINKSTATUS, and the value is one of the ZFLINK_??? values listed below.
LocalLinkStatus	Current status of the local server on the link. This is a variable of type ZFLINKSTATUS, and the value is one of the ZFLINK_??? values listed below.
fConnectionOK	Current status of the connection (mail or WAN) to the remote server. This is a Boolean value, 1 for a good connection, 0 for no
fLinkActive	connection. This is a Boolean value indicating whether the link is active, and available for sending and receiving (1 if the link is active, 0 if the link is not active). This value is computed from RemoteLinkStatus, LocalLinkStatus and fConnectionOK
NumSentOK	fields. Number of messages sent
NumTimedOut	successfully by the remote server. Number of messages timed out
NumRejected	waiting for responses over the link. Number of messages rejected by
NumDeviceError	the remote server. Number of messages failed to be sent by the remote server as a
NumRemoteServerErr	result of device errors. Number of messages failed to be sent by the remote server as a result of other errors at the remote
NumUnack	server. Number of messages submitted to the remote server and still awaiting
NumAck	acknowledgement. Number of messages submitted to the remote server and
NumReceived	acknowledged. Number of messages received from

the remote server for sending locally.

Link status

The following list gives the possible status values for a link (variable of type ZFLINKSTATUS).

Field ZFLINK_UNKNOWN_STATE	Description Remote link status unknown. This occurs when the Zetafax server has not received any communication from the remote server.
ZFLINK_INITIALISING ZFLINK_ONLINE	Link is currently being initialised. Link is online.
ZFLINK_OFFLINE	Link has been set to offline by the administrator, and is unavailable for sending.
ZFLINK_FAILED_WDOG	The link watchdog failed to receive an expected message.
ZFLINK_SHUTDOWN ZFLINK_UNRECOGNISED_STATE	The link has been shut down. Unrecognised state. This could occur if an API program is run with a later version of the Zetafax server which supports additional link states.

1 top

Related topics

<u>Function overview</u> <u>Function error returns and reference</u> <u>Alphabetical reference</u> <u>Message information functions</u> <u>Message transmission history functions</u> <u>Converting from older versions of the API</u>

1 top



Function error returns and reference

Return ZFERR_BUFFER_TOO_SMALL	Description One of the buffer lengths specified in the call is smaller than the length of
ZFERR_CANNOT_LOG_ON	the string which is to be returned. Increase the buffer length. The user specified in the ZfxAPIInit call is already logged on (and the 'exclusive' option was specified), or
ZFERR_CANNOT_READ_MSG_ DEFAULTS	the program has insufficient access permissions to the user directories. Unable to read the default settings for this user contained in the USER. INI files. Check the program has read access to the SYSTEM\Z-DB
ZFERR_CANNOT_RUN_SYSTEM_ MANAGER	program SYSMAN.EXE. Check the file exists in the ServerArea (as
ZFERR_CANNOT_SUBMIT_ REQUEST	specified in the ZETAFAX.INI file) Error submitting request to the Zetafax server. Check access permissions to the REQUEST
ZFERR_CONTROL_FILE_ERROR	directory. Error reading or writing CONTROL
ZFERR_CONTROL_FILE_INVALID ZFERR_CONTROL_FILE_OPEN_ERROR	file. CONTROL file is corrupt. Unable to open the CONTROL file. Check the file exists, and that the
ZFERR_ERROR_STARTING_SERVER	program has sufficient access permissions. General error starting the server. The error is logged to the SERVER. LOG file in the SERVER\Z-DB
ZFERR_FILE_CREATE_ERROR	directory. Unable to create the specified file. Check the path and file name are valid, and that the program has sufficient access rights to the
ZFERR_FILE_ERROR	directory. Unable to read from or write to the specified file. Check the path and file name are valid, the file exists,
ZFERR_FILE_NOT_FOUND	and that the program has sufficient access rights to the directory. The specified file does not exist. Check the path and file name are valid, the file exists, and that the
ZFERR_FILE_OPEN_ERROR	program has sufficient access rights to the directory. Unable to open the specified file. Check the path and file name are valid, the file exists, and that the
ZFERR_FUNCTION_ABORTED	program has sufficient access rights to the directory. The function has failed because a user supplied callback function has

	returned an "abort and stop waiting" status.
ZFERR_INFO_FILE_ERROR	Error reading or writing MSGDIR.CTL file.
ZFERR_INFO_FILE_INVALID	MSGDIR.CTL file is corrupt.
ZFERR_INFO_FILE_OPEN_ERROR	Unable to open the MSGDIR.CTL file. Check the file exists, and that the
	program has sufficient access
	permissions.
ZFERR_INVALID_DATA_FORMAT	The data file format specified is
	unknown. Check the parameter and file type.
ZFERR INVALID PARAMETERS	One or more of the parameters given
	to the routine has an invalid format
	(eg file name too long). Check the
ZFERR INVALID ZF INIT FILE	parameters. The server directories could not be
	determined from the ZETAFAX.INI
	file. Check the file has not been
	corrupted, and if necessary reinstall
ZFERR MESSAGE ALREADY EXISTS	the server or client on the PC. The message specified in the
	ZfxSendMsgEx call is already
	referenced in the INFO file. This can
	happen if a message file is deleted
	manually without calling ZfxDeleteMsg to delete the
	references, or if an existing control
	file is overwritten by a new one
	created without using the
	ZfxCreateAutoFile routine to ensure no files of the given name already
	exist. Call ZfxAbortMsg if the status
	is not OK or FAILED (to delete the
	message from server queues), call ZfxDeleteMsg and try again.
ZFERR MESSAGE NOT COMPLETED	The message specified in the
	ZfxDeleteMsg call is still being
	processed by the server. Call
	ZfxAbortMsg first, then wait for the state to change to ZFMSG OK or
	ZFMSG_FAILED.
ZFERR_NO_ZF_INIT_FILE	Initialization file ZETAFAX.INI not
	found. The directory containing this is normally given in the environment
	variable ZFAXINIT. Check that this
	variable exists in the environment -
	for an OS/2 program being run
	detached or from the program manager the SET ZFAXINIT= line
	must have been added to the
	CONFIG.SYS file, and the PC
	rebooted before the change will be
ZFERR NOT INITIALISED	noted. The ZfxAPIInit routine has not been
	called successfully. This must be
ZEEDD DATH NOT FOUND	done before calling the given routine. The given path or file does not exist
ZFERR_PATH_NOT_FOUND	ZFERR SERVER INI FILE ERROR
	Server initialisation file SETUP.INI
TEED CEDVED NOT DURING	not found or invalid.
ZFERR_SERVER_NOT_RUNNING	The Zetafax server is not running, or the program is unable to
	communicate with the server. Check
	that the server has not been
	stopped, and that the program has

157

ZFERR_SERVER_RUNNING	sufficient access to the server REQUEST directory. Some or all of the server programs are already running. The server must be completely stopped before the ZfxStartServer function or ZfxDeleteMsg function (specifying all
ZFERR_SUBMIT_FILE_INVALID	messages) can be used. One or more lines in the SUBMIT file specified are invalid. The error text given in the ZfxPrintError call details the line at fault.
ZFERR_TIMEOUT_EXPIRED	The specified function has not completed within the timeout period.
ZFERR_TOO_MANY_FILES	Too many files (ie 1000) of the format specified in the ZfxCreateAutoFile call already exist, and a new one can not be created.
ZFERR_UNKNOWN_MESSAGE	The control file for the message specified does not exist, or it is not referenced in the INFO file.
ZFERR_UNKNOWN_USER	The Zetafax username given in the ZfxAPIInit call has not been configured on the Zetafax system.

Related topics

Function overview Alphabetical reference Message information functions Message transmission history functions Server and device status functions Converting from older versions of the API



Alphabetical reference

There follows a description of all of the routines available within the Zetafax C language API. Each routine includes some example code showing how it may be called from within your application.

User supplied error message display function

<u>ZfxAbortMsg</u>

ZfxAPIInit

ZfxCheckNewMsgStatus

ZfxCheckServer

ZfxAPIClosedown

ZfxCreateAutoFile

ZfxCreateCtlFile

<u>ZfxCreateCtlFileEx</u>

ZfxCreateCtlFileFP

<u>ZfxCreateDataFile</u>

ZfxCreateDataFileFP

ZfxDeleteMsg

ZfxGetAPIVersion

<u>ZfxGetMsgDefaultsEx</u>

ZfxGetMsgInfo

<u>ZfxGetMsgInfoEx</u>

<u>ZfxGetMsgHistory</u>

<u>ZfxGetMsgHistoryEx</u>

<u>ZfxGetMsgList</u>

<u>ZfxGetMsgListEx</u>

<u>ZfxGetServerStatus</u>

ZfxGetServerStatusEx

ZfxGetSystemArea

<u>ZfxGetUserArea</u>

<u>ZfxGetUserCoversheet</u>

ZfxGetUserFromname

C language API	159

ZfxGetUserInDir

<u>ZfxGetUserOutDir</u>

<u>ZfxHoldMsg</u>

ZfxMarkMsgAsRead

<u>ZfxReleaseMsg</u>

<u>ZfxRestartServer</u>

<u>ZfxRushMsg</u>

ZfxSendMsg

<u>ZfxSendMsgEx</u>

ZfxSendSubmitFile

ZfxSendSubmitFileFP

<u>ZfxStartServer</u>

<u>ZfxStopServer</u>

ZfxVBSendSubmitFile

Related topics

Function error returns and reference Message information functions Message transmission history functions Server and device status functions Converting from older versions of the API

160 Zetafax 2012 API Help



User supplied error message display function

Syntax

void ZFAPICALLBACK MyError(char FAR *lpszErrorText)

Parameters

 Parameter
 Description

 lpszErrorText
 Null terminated string containing explanatory text for error

Description

This routine should be defined within the application program itself - it can have any name. Its address is passed as one of the parameters to ZfxAPIInit , and it is called by the API before the API routines return certain error codes, to give additional text explaining why the call failed. For example, if a SUBMIT file is rejected the API will call this routine with the reason, before returning the error code ZFERR_SUBMIT_FILE_INVALID.

For programs which interact with the user the text is probably best displayed on screen, as an additional help to any error message which the program itself may display as a result of the returned error code. Other programs may wish to log the error to disk or ignore it (defining an empty function) as required. Note that a FAR (32-bit) pointer to the string is supplied - in 16 bit environments the "%Fs" (or equivalent) format specifier will be needed in calls to printf etc.

Return Value

There is no return value.

Example

```
#include <stdio.h>
#include <zfapi.h>
...
void ZFAPICALLBACK DisplayAPIError( char FAR *lpszText)
{
    /* Note - remember to use %Fs in 16 bit */
    /* programs because it is a FAR pointer */
    printf("*API ERROR* %Fs\n", lpszText);
}
```

Related topics

Alphabetical reference Function error returns and reference



ZfxAbortMsg

Gets the default message settings for the user.

Syntax

ZFERR FAR ZfxAbortMsg(ZFSESSIONHANDLE hSession, ZFMSGDIR MsgDir, char FAR *lpszBody)

Parameters

ParameterDescriptionHsessionAPI session handle, as returned by
ZfxAPIInit callMsgDirMessage type (ZFDIR_OUT)
name of message file

Description

This routine is called to stop the server processing a message after it has been submitted using ZfxSendMsgEx . The routine sends a request to the Zetafax server, which processes it asynchronously. The routine can be called even if the server has already finished processing the message.

Return value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_UNKNOWN_MESSAGE ZFERR_SERVER_NOT_RUNNING ZFERR_CANNOT_SUBMIT_REQUEST

Example



ZfxAPIClosedown

Closedown API routines.

Syntax

ZFERR FAR ZfxAPIClosedown(ZFSESSIONHANDLE hSession)

Parameters

Parameter Description hSessionAPI session handle, as returned by ZfxAPIInit call

Description

This routine should be called for each session handle returned by $\mathsf{Zfx}\mathsf{APIInit}$. It releases any resources used by the API routines.

Return value

The routine returns 0.

Example



ZfxAPIInit

Initialise Zetafax API.

Syntax

ZFERR FAR ZfxAPIInit(ZFSESSIONHANDLE *phSession, char FAR *lpszUserName, short fExclusive, ZFERRORPROC *lpErrorProc)

Parameters

Parameter phSession	Description Address of variable of type ZFSESSIONHANDLE, used to return the API session handle. This handle should then be passed to other API functions to identify the session.
lpszUserName	Zetafax username to use when submitting messages fExclusiveZero if this user is permitted to be logged on elsewhere (either on a normal Zetafax client, or in another API program).
lpErrorProc	Address of error message callback function, called when an error occurs with a text string if there is additional information relating to the error. This can be set to NULL if not required.

Description

This routine should be called before calling any of the other API functions. The routine may be called more than once by the program if it wishes to log on as more than one user. The paired routine ZfxAPIClosedownshould be called for each handle returned by this function before exiting from the program.

If the fExclusive flag is set (non-zero), then each call to this function may result in a "lock" file being kept open until ZfxAPIClosedown is called. Because most programs have a limit to the total number of files which may be kept open, it is recommended that you only have one session open at a time if fExclusive is set - ie ZfxAPIClosedown is always called before calling ZfxAPIInit again.

Return value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_INVALID_PARAMETERS ZFERR_NO_ZF_INIT_FILE ZFERR_INVALID_ZF_INIT_FILE ZFERR_UNKNOWN_USER ZFERR_CANNOT_LOG_ON Zetafax 2012 API Help

Function error returns and reference

Example

164

```
#include <stdio.h>
#include <zfapi.h>
. . .
ZFERR Err;
ZFSESSIONHANDLE hSession;
/* Log on as FRED, which sets hSession if ok */
Err = ZfxAPIInit(&hSession, "FRED", TRUE, MyErrorProc);
if (Err == 0)
 {
        /* call required functions */
       . . .
       /* cleanup */
       ZfxAPIClosedown(hSession);
 }
 else
 {
       printf("Unable to log in as FRED\n");
 }
Related topics
Alphabetical reference
```

© 2012 Equisys plc

ZfxCheckNewMsgStatus

Check if message status has changed.

Syntax

ZFERR FAR ZfxCheckNewMsgStatus(ZFSESSIONHANDLE hSession, ZFMSGDIR MsgDir, short FAR *lpfStatusChanged)

Parameters

Parameter hSession	Description API session handle, as returned by ZfxAPIInit call MsgDirMessage type - ZFDIR_OUT for sent messages, or ZFDIR_IN for received messages
lpfStatus	Changed Address of short integer boolean variable which is set to a non-zero value if the status of one or more messages may have changed since the last call to this function, 0 otherwise 1.

Description

This routine checks whether the status of any of the messages in the current users OUT or IN directory (depending on the setting of MsgDir) has changed. If the fStatusChanged variable is set (non-zero) on return then the calling program should call the ZfxGetMsgInfoEx routine for each message it is interested in (or the ZfxGetMsgListExto get information for all messages) to identify what (if anything) has changed.

This function is supplied because ZfxGetMsgInfoEx and ZfxGetMsgListEx stop the server updating the status of any messages for that user while running, and should therefore only be called when necessary. The ZfxCheckNewMsgStatus function acts by checking the attributes of a file, and therefore it is recommended that it is not called more frequently than every 5 to 10 seconds unless a quicker response is required.

Return value

The routine returns 0 if successful, otherwise one of the following:

```
ZFERR_NOT_INITIALISED
ZFERR_INFO_FILE_ERROR
```

Example

}

```
...
}
/* sleep for a few seconds */
```



ZfxCheckServer

Check server running.

Syntax

ZFERR FAR ZfxCheckServer(ZFSESSIONHANDLE hSession)

Parameters

Parameter hSession

Description API session handle, as returned by ZfxAPIInit call

Description

This routine checks whether the Zetafax server is running. The server must be running before messages can be submitted for sending.

Return value

The routine returns 0 if the server is running correctly, otherwise one of the following:

```
ZFERR_NOT_INITIALISED
ZFERR_SERVER_NOT_RUNNING
```

Example

```
#include <stdio.h>
#include <zfapi.h>
...
if (ZfxCheckServer(hSession) != 0)
{
    printf("Problem checking Zetafax server\n");
}
```


ZfxCreateAutoFile

Creates file name with unique body.

Syntax

ZFERR FAR ZfxCreateAutoFile(ZFSESSIONHANDLE hSession, char FAR *lpszPrefix, char FAR *lpszExtn, char FAR *lpszPath, char FAR *lpszBody)

Parameters

Parameter	Description
hSession	API session handle, as returned by
	ZfxAPIInit call lpszPrefix4 character
	identifier for filelpszExtn1 to 3
	character extension for file
lpszPath	Full pathname of directory to contain
	filelpszBodyAddress of buffer (of
	length ZFMSG_BODY_LEN+1) to
	receive body name of file which is
	created (returned)

Description

This routine creates a file in the given directory, where no other file in the directory has the same body name (ie the part of the file name excluding the extension). The file name created has the form "~ppppnnn.xxx" where pppp and xxx are the prefix name and extension specified in the call, and nnn is a number from 000 to 999 (or can be 3 alphanumeric characters if the directory already contains a large number of matching files).

The routine is used when creating message files to be sent, since each message has a unique body name. It is recommended that the first character of the base name chosen is "X" to guarantee that files created by application programs are not confused with ones created by the Zetafax client (although this is not mandatory).

Return value

The routine returns 0 if successful, otherwise one of the following:

```
ZFERR_NOT_INITIALISED
ZFERR_INVALID_PARAMETERS
ZFERR_PATH_NOT_FOUND
ZFERR_TOO_MANY_FILES
ZFERR_FILE_CREATE_ERROR
```

Example

```
#include <stdio.h>
#include <stdio.h>
#include <zfapi.h>
...
char szBody[ZFMSG_BODY_LEN+1];
char szUserOutDir[256];
if (ZfxGetUserOutDir(hSession, szUserOutDir, sizeof(szUserOutDir)) == 0 &&
ZfxCreateAutoFile(hSession, "XSUB", "TMP", szUserOutDir, szBody) == 0)
{
```

```
printf("Created file %s%s.TMP\n", szUserOutDir, szBody);
```

Related topics Alphabetical reference Function error returns and reference

}



ZfxCreateCtlFile

Create a CONTROL file from SUBMIT format file.

Syntax

ZFERR FAR ZfxCreateCtlFile(ZFSESSIONHANDLE hSession, char FAR *lpszSubmitFile, char FAR *lpszControlFile, char FAR *lpszBody, char FAR *lpszDataExtn, char FAR *lpszDataExtnBuf, char FAR *lpszCommentBuf)

Parameters

Parameter hSession	Description API session handle, as returned by ZfxAPIInit call lpsz
SubmitFile	Name of submit file (with path if not in current directory)
lpszControl	FileName of new CONTROL file (with path if not in current directory)
lpszBody	Data file extension for the required format, or NULL to use the default (or to allow the Syntax line in the SUBMIT file to overwrite the default).
lpszDataExtn	IpszDataExtnBufAddress of buffer of length 4 bytes. On return this will contain the data file extension to use. If the IpszDataExtn parameter was given as NULL then this will give the data format specified in the Syntax line in the SUBMIT file (or the default value of TXT for straight ASCII text if this line is not specified). If the IpszDataExtn was specified then an error is returned if the SUBMIT file contains a Syntax line which contradicts this.
lpszCommentBuf	contradicts this. Address of buffer of length ZFMSG_COMMENT_LEN+1 used to return the message comment for specifying in a subsequent ZfxSendMsg call.

Description

This routine interprets the %%[MESSAGE] of a given SUBMIT format file, writing the details to the given CONTROL file. It is used where the ZfxSendSubmitFile function does not give sufficient flexibility - for example when wishing to send an existing data file.

NOTE - this function is supplied for compatibility with version 5 of the Zetafax API only. Version 6 API applications should use ZfxCreateCtlFileEx.

Return value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_FILE_ERROR ZFERR_FILE_OPEN_ERROR ZFERR_FILE_CREATE_ERROR ZFERR_SUBMIT_FILE_INVALID

Example

```
#include <stdio.h>
#include <zfapi.h>
 . . .
/* create .CTL file in user's OUT directory */
ZfxGetUserOutDir(hSession, szOutDir, sizeof(szOutDir);
ZfxCreateAutoFile(hSession, "XSUB", "CTL", szOutDir, szBody); continued.
/* get name of the CTL file we've just created */
sprintf(szPath, "%s%s.CTL", szOutDir, szBody);
/* interpret the SUBMIT file created earlier */
/* to send an existing file of format G3F */
ZfxCreateCtlFile(hSession, "MYFILE.SUB", szPath, szBody, "G3F", szDataExtn,
szComment);
/* Create data file in OUT directory */
sprintf(szPath, "%s%s.G3F", szOutDir, szBody);
 . . .
/* submit files */
ZfxSendMsg(hSession, szBody, "G3F", szComment);
```

equisys ZETA/AX[®]

ZfxCreateCtlFileEx

Create a CONTROL file from SUBMIT format file.

Syntax

ZFERR FAR ZfxCreateCtlFileEx(ZFSESSIONHANDLE hSession, char FAR *lpszSubmitFile, char FAR *lpszControlFile, char FAR *lpszDataExtn, char FAR *lpszDataExtnBuf, short MsgInfoExSize, ZFMSGINFOEX FAR *lpMsgInfoEx)

Parameters

Parameter hSession	Description API session handle, as returned by ZfxAPIInit call lpszSubmitFileName of submit file (with path if not in current directory)
lpszControl	FileName of new CONTROL file (with path if not in current directory)lpszDataExtnData file extension for the required format, or NULL to use the default (or to allow the Syntax line in the SUBMIT file to
lpszDataExtnBuf	overwrite the default). Address of buffer of length 4 bytes. On return this will contain the data file extension to use. If the lpszDataExtn parameter was given as NULL then this will give the data format specified in the Syntax line in the SUBMIT file (or the default value of TXT for straight ASCII text if this line is not specified). If the lpszDataExtn was specified then an error is returned if the SUBMIT file contains a Syntax line which contradicts this.
MsgInfoExSize	Size of structure - should be set to sizeof(ZFMSGINFOEX) lpMsgInfoEx Address of a single ZFMSGINFOEX structure, which is filled with the details of the message (body, comment etc) on return.

Description

This routine interprets the %%[MESSAGE] of a given SUBMIT format file, writing the details to the given CONTROL file. It is used where the ZfxSendSubmitFile function does not give sufficient flexibility - for example when wishing to send an existing data file.

Return value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_FILE_ERROR ZFERR_FILE_OPEN_ERROR ZFERR_FILE_CREATE_ERROR ZFERR_SUBMIT_FILE_INVALID

Example

```
#include <stdio.h>
#include <zfapi.h>
/* create .CTL file in user's OUT directory */
ZfxGetUserOutDir(hSession, szOutDir, sizeof(szOutDir));
ZfxCreateAutoFile(hSession, "XSUB", "CTL", szOutDir, MsgInfoEx.szBody);
/* get name of the CTL file we've just created */
sprintf(szPath, "%s%s.CTL", szOutDir, MsgInfoEx.szBody);
/* interpret the SUBMIT file created earlier */
/* to send an existing file of format G3F */
ZfxCreateCtlFileEx(hSession, "MYFILE.SUB", szPath, "G3F", szDataExtn, sizeof
(ZFMSGINFOEX), &MsgInfoEx);
/* Create data file in OUT directory */
sprintf(szPath, "%s%s.G3F", szOutDir, MsgInfoEx.szBody);
. . .
/* submit files */
ZfxSendMsgEx(hSession, "G3F", sizeof(ZFMSGINFOEX), &MsgInfoEx);
```

ZfxCreateCtlFileFP

Create a CONTROL file (old version).

Syntax

ZFERR FAR ZfxCreateCtlFileFP(ZFSESSIONHANDLE hSession, FILE *fpSubmit, FILE *fpControl, char FAR *lpszBody, char FAR *lpszDataExtn, char FAR *lpszDataExtnBuf, char FAR *lpszCommentBuf)

Parameters

	ameter Assion	Description API session handle, as returned by ZfxAPIInit call fpSubmit File pointer for SUBMIT format file, opened in binary mode with read access (eg an "rb" parameter to the fopen call). The file pointer should be positioned at the start of the %%[MESSAGE] line. On return the file pointer is positioned at the start of the next line found in the file which starts with "% %" (signifying the end of the %%MESSAGE section) if one exists, or the end of file otherwise.fpControl File pointer for new CONTROL file, opened with in binary mode with write access.
lpsz	Body	Message body name (base name of control and data file) IpszDataExtn-Data file extension for the required format, or NULL to use the default (or to allow the Syntax line in the SUBMIT file to overwrite the default).
lpsz	DataExtnBuf	Address of buffer of length 4 bytes. On return this will contain the data file extension to use. If the lpszDataExtn parameter was given as NULL then this will give the data format specified in the Syntax line in the SUBMIT file (or the default value of TXT for straight ASCII text if this line is not specified). If the lpszDataExtn was specified then an error is returned if the SUBMIT file contains a Syntax line which contradicts this.
lpsz	Comment	Buf Address of buffer of length ZFMSG_COMMENT_LEN+1

Equisys

used to return the message comment for specifying in a subsequent ZfxSendMsg call.

Description

This routine interprets the %%[MESSAGE] of a given SUBMIT format file, writing the details to the given CONTROL file. It is used where the ZfxSendSubmitFile function does not give sufficient flexibility - for example when wishing to send an existing data file. NOTE - this routine is supplied for historic reasons to assist porting applications written for an older version of the API. Because of its use of file pointers is only supported in the static library version of the API, not the DLL. New programs should use the ZfxCreateCtlFileEx function instead.

Return value

The routine returns 0 if successful, otherwise one of the following:

```
ZFERR_NOT_INITIALISED
ZFERR_INVALID_PARAMETERS
ZFERR_FILE_ERROR
ZFERR_SUBMIT_FILE_INVALID
```

Example

```
#include <stdio.h>
#include <zfapi.h>
 . . .
/* create .CTL file in user's OUT directory */
ZfxGetUserOutDir(hSession, szOutDir, sizeof(szOutDir);
ZfxCreateAutoFile(hSession, "XSUB", "CTL", szOutDir, szBody);
/* open the CTL file we've just created */
sprintf(szPath, "%s%s.CTL", szOutDir, szBody);
fpCtl = fopen(szPath, "wb");
/* interpret the SUBMIT file created earlier */
/* to send an existing G3F format file */
ZfxCreateCtlFileFP(hSession, fpSubmit, fpCtl, szBody, "G3F", szDataExtn, szComment);
fclose(fpCtl);
/* Create data file in OUT directory */
sprintf(szPath, "%s%s.G3F", szOutDir, szBody);
 . . .
```

```
/* submit files */
ZfxSendMsg(hSession, szBody, "G3F", szComment);
```

Related topics

<u>Alphabetical reference</u> <u>Function error returns and reference</u>



ZfxCreateDataFile

Create a DATA file from SUBMIT format file.

Syntax

ZFERR FAR ZfxCreateDataFile(ZFSESSIONHANDLE hSession, char FAR *lpszSubmitFile, char FAR *lpszDataFile, char FAR *lpszDataExtn)

Parameters

ParameterDescriptionhSessionAPI session handle, as returned
by ZfxAPIInit calllpszSubmitFileName of submit file (with path if
not in current directory)
lpszDataFileName of new DATA
file (with path if not in current
directory) lpszDataExtnData file
extension for the required format
- either "TXT" for ASCII text, or
"EPN" for Epson print format.

Description

This routine interprets the %%[TEXT] of a given SUBMIT format file, writing the details to the given CONTROL file. It is used where the ZfxSendSubmitFile function does not give sufficient flexibility - for example when wishing to send an existing data file.

Return value

The routine returns 0 if successful, otherwise one of the following: ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_FILE_OPEN_ERROR ZFERR_FILE_CREATE_ERROR ZFERR_FILE_ERROR ZFERR_SUBMIT_FILE_INVALID

Example

#include <stdio.h>
#include <stdio.h>
#include <zfapi.h>
...
/* create .CTL file in user's OUT directory */
...
/* Create data file in OUT directory */
sprintf(szPath, "%s%s.EPN", szOutDir, szBody);
ZfxCreateDataFile(hSession, "MYFILE.SUB", szPath, "EPN");
/* submit files */
...



ZfxCreateDataFileFP

Create a DATA file (old version).

Syntax

ZFERR FAR ZfxCreateDataFile(ZFSESSIONHANDLE hSession, FILE *fpSubmit, FILE *fpData, char FAR *lpszDataExtn)

Parameters

Parameter hSession	Description API session handle, as returned by ZfxAPIInit call
fpSubmit	File pointer for SUBMIT format file, opened in binary mode with read access (eg an "rb" parameter to the fopen call). The file pointer should be positioned at the start of the %%[TEXT] line. The routine interprets all the file from the current position to the end of the file, treating the contents as the message to be sent.
fpData	File pointer for new DATA file, opened in binary mode with write access.
lpszDataExtn	

Description

This routine interprets the %%[TEXT] of a given SUBMIT format file, writing the details to the given CONTROL file. It is used where the ZfxSendSubmitFile function does not give sufficient flexibility - for example when wishing to send an existing data file.

NOTE - this routine is supplied for historic reasons to assist porting applications written for an older version of the API. Because of its use of file pointers is only supported in the static library version of the API, not the DLL. New programs should use the ZfxCreateDataFile function instead.

Return Value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_FILE_ERROR ZFERR_SUBMIT_FILE_INVALID

Example

```
#include <stdio.h>
#include <zfapi.h>
...
```

```
Zetafax 2012 API Help
```

178

```
/* create .CTL file in user's OUT directory */
...
/* create data file */
sprintf(szPath, "%s%s.EPN", szOutDir, szBody);
fpData = fopen(szPath, "wb");
ZfxCreateDataFileFP(hSession, fpSubmit, fpData, "EPN");
fclose(fpData);
/* submit files */
...
```



ZfxDeleteMsg

Delete message entry.

Syntax

ZFERR FAR ZfxDeleteMsg(ZFSESSIONHANDLE hSession, ZFMSGDIR MsgDir, char FAR *lpszBody, short fDeleteFiles)

Parameters

Parameter	Description
hSession	API session handle, as returned by ZfxAPI
Init call MsgDir	Message type - ZFDIR_OUT for sent messages, or ZFDIR_IN for received messages
lpszBody	Message body name - NULL to delete all messages for this user fDeleteFilesBoolean, non-zero if the control and data files (and any other temporary files created by the server) for the message are to be deleted, in addition to removing the message entry from the INFO file.

Description

This routine is called to remove the entry for a given message from the OUT or IN directory message INFO file, and optionally to delete the associated data files. If the server is stopped and the body name is specified as NULL then this routine will reset the specified directory (and its subdirectories) to delete all entries from the queue. Note that if the fDeleteFiles flag is set in this case all files will be deleted from the OUT directory and its subdirectories or the Z-IN directory, and a new empty INFO file generated.

Return value

The routine returns 0 if successful, otherwise one of the following: ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_SERVER_NOT_RUNNING ZFERR_UNKNOWN_MESSAGE ZFERR_INFO_FILE_OPEN_ERROR ZFERR_INFO_FILE_ERROR ZFERR_INFO_FILE_INVALID ZFERR_MESSAGE_NOT_COMPLETED ZFERR_SERVER_RUNNING

Example

```
#include <stdio.h>
#include <zfapi.h>
...
```

180

```
/* following call fails if message status not */
/* ZFMSG_FAILED or ZFMSG_OK */
if (ZfxDeleteMsg(hSession, ZFDIR_OUT, "~XSND000", TRUE) == 0)
{
    printf("Message deleted\n");
}
```


ZfxGetAPIVersion

Get version identifier for API routines.

Syntax

ZFERR FAR ZfxGetAPIVersion(char FAR *lpszBuffer, short BufLen, unsigned short FAR *lpusVersion)

Parameters

Description
Address of buffer to store version
identifier string, or NULL if not
required. BufLenLength of buffer
(including space for terminating null)
Address of unsigned short integer
variable used to return the version
number of the API routines, or NULL
if not required.

Description

This routine gets a version identifier for the API routines. The version identifier is 20 characters or fewer (generally about 5 characters plus terminating null), and may be used when displaying the version number an application program.

The numeric version number will allow future programs to detect when they are running with an older version of the API. This is currently set to 0x600 (hex) - it is recommended that programs do not object if this number is higher than expected to allow for future updates to the API without the need to rebuild the programs.

Return value

The routine returns 0 if successful, otherwise one of the following: ${\sf ZFERR_BUFFER_TOO_SMALL}$

Example

```
#include <stdio.h>
#include <stdio.h>
#include <zfapi.h>
...
char szVersion[20+1];
unsigned short usVersion;
printf("Automatic invoicing program v2.27\n");
if (ZfxGetAPIVersion(szVersion, sizeof(szVersion), &usVersion) == 0)
{
    printf("Zetafax API version %s\n", szVersion);
}
Deletedence
```

Related topics Alphabetical reference Zetafax 2012 API Help

Function error returns and reference

ZfxGetMsgDefaultsEx

Gets the default message settings for the user.

Syntax

ZFERR FAR ZfxGetMsgDefaultsEx(ZFSESSIONHANDLE hSession, short MsgDefaultsExSize, ZFMSGDEFAULTSEX *lpMsgDefaultsEx)

Parameters

Parameter Hsession	Description API session handle, as returned by ZfxAPIInit call MsgDefaultsExSize Size of ZFMSGDEFAULTSEX structure. Must be the size (in bytes) of a ZFMSGDEFAULTSEX structure Pointer to memory allocated for a
	ZFMSGDEFAULTSEX structure

Description

This routine is called to get the default message settings for the Zetafax user associated with the API session associsted with the passed session handle.

Return value

The routine returns 0 if successful, otherwise one of the following: ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS

Example

```
#include <stdio.h>
#include <stdio.h>
#include <zfapi.h>
...
ZFMSGDEFAULTSEX ZfMsgDefaults;
memset(&ZfMsgDefaults, (int) 0, sizeof(ZFMSGDEFAULTSEX)
if (ZfxGetMsgDefaultsEx(hSession, sizeof(ZFMSGDEFAULTSEX), &ZfMsgDefaults) == 0)
{
    /* 'ZfMsgDefaults' structure now */
    /* contains the default message */
    /* settings for the user */
    printf("Default message priority is %d\n", ZfMsgDefaults.Priority); ...
}
```

Related topics Alphabetical reference Function error returns and reference ZFGetMSGDEFAULTSEX structure

equisys ZETA/AX[®]

ZfxGetMsgHistory

Get transmission history information for message.

Syntax

ZFERR FAR ZfxGetMsgHistory(ZFSESSIONHANDLE hSession, ZFMSGDIR MsgDir, char FAR *lpszBody, short AddrNum, short fAllEvents, short MaxEntries, short FAR *lpNumEntries, short MsgHistorySize, ZFMSGINFO FAR *lpMsgHistory)

Parameters

Parameter hSession	Description API session handle, as returned by ZfxAPIInit call MsgDirMessage type - ZFDIR_OUT for sent messages, or ZFDIR_IN for received messages
lpszbody	Message file body AddrNumWhich addressee events are required for (first addressee is number 1), or 0 to retrieve events for all addressees.
fAllEvents	Non zero if events of type ZFEVENT_TRIED are to be included, otherwise only "final state" events are included.
MaxEntries	Maximum number of entries to be returned (ie number of elements in the arrays which follow)
IpNumEntries	Address of short integer variable used to return the number of events in the file. Note that the returned value may be larger than the value given for MaxEntries if the buffer was not large enough for all entries.
MsgHistorySize	Size of structure - should be set to sizeof (ZFMSGHISTORY) lpMsgHistoryAddress of array of 'n' ZFMSGHISTORY structures, where 'n' is the value given by the MaxEntries parameter

Description

This routine gets a list of the transmission history entries in the CONTROL file for a given message, giving the information about transmission attempts (result, connection time etc).

C language API	185
----------------	-----

If the number of entries in the list exceeds the MaxEntries parameter, then the routine returns information about the first MaxEntries entries, but sets the IpNumEntries parameter to the total number of entries in the list. Be careful therefore to only read the lesser of (MaxEntries) and (IpNumEntries) elements of the array on return. Calling the routine with MaxEntries set to 0 will just return a count of the number of entries.

The fAllEvents flag can be used to specify whether all dial and transmission attempts should be included, or just the final status. If only the final status for a given addressee is required then the function can be called with the fAllEvents flag set to FALSE (0), and a single ZFMSGHISTORY buffer (MaxEntries = 1). The routine opens and reads the CONTROL file for the message. This is the file that is updated by the Zetafax server while the message is in its queue. It is therefore necessary to protect against calling this routine too frequently while the entry is in the server queue. Use ZfxCheckNewMsgStatus and ZfxGetMsgInfo to wait until the message has completed before calling this routine.

NOTE - this function is supplied for compatibility with version 5 of the Zetafax API only. Version 6 API applications should use ZfxGetMsgHistoryEx.

Return value

The routine returns 0 if successful, otherwise one of the following: ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_CONTROL_FILE_OPEN_ERROR ZFERR_CONTROL_FILE_ERROR ZFERR_CONTROL_FILE_INVALID

Example

```
#include <stdio.h>
#include <zfapi.h>
 . . .
#define LIST_SIZE 20
ZFMSGHISTORY aMsgHistory[LIST_SIZE];
Err = ZfxGetMsqHistory(hSession, ZFDIR_OUT, "~SEND000", 1, TRUE, LIST_SIZE,
&NumEntries, sizeof(ZFMSGHISTORY), MsgHistory);
if (Err != 0)
 {
       return;
 }
if (NumEntries > LIST_SIZE)
 {
       printf("Total messages %d\n", NumEntries); printf("Displaying first %d\n",
LIST_SIZE);
 }
for (Entry = 0, Tries = 1; Entry < min(NumEntries, LIST_SIZE); Entry++)</pre>
 {
       switch(aMsgHistory[Entry]->EventType)
       {
              case ZFEVENT_TRIED: Tries++;
                     printf("Tried unsuccessfully\n");
              break;
              case ZFEVENT_SENT_OK:
                     Tries++;
                     printf("Sent OK on attempt %d\n" Tries);
                     printf("Connect time %d secs\n", MsgHistory[Event].ConnectSecs);
              break;
              case ZFEVENT_SENT_ERROR:
                     Tries++;
```

186

}

```
printf("Failed after %d attempts\n", Tries);
                    printf("Pages sent %d\n", aMsgHistory[Event].Pages);
             break;
             default:
             /* ignore other events */
             break;
      }
Related topics
```

Alphabetical reference Function error returns and reference



ZfxGetMsgHistoryEx

Get transmission history information for message.

Syntax

ZFERR FAR ZfxGetMsgHistoryEx(ZFSESSIONHANDLE hSession, ZFMSGDIR MsgDir, char FAR *lpszBody, short AddrNum, SHORT fAllEvents, short MaxEntries, short FAR *lpNumEntries, short MsgHistoryExSize, ZFMSGHISTORYEX FAR *lpMsgHistoryEx)

Parameters

Parameter hSession	Description API session handle, as returned by ZfxAPIInit call MsgDirMessage type - ZFDIR_OUT for sent messages, or ZFDIR_IN for received messages
lpszbody	Body of message file to get history forAddrNumWhich addressee events are required for (first addressee is number 1), or 0 to retrieve events for all addressees.
fAllEvents	Non zero if events of type ZFEVENT_TRIED are to be included, otherwise only "final state" events are included. MaxEntriesMaximum number of entries to be returned (ie number of elements in the arrays which follow)
IpNumEntries	Address of short integer variable used to return the number of events in the file. Note that the returned value may be larger than the value given for MaxEntries if the buffer was not large enough for all entries.
MsgHistoryExSize	Size of structure - should be set to sizeof (ZFMSGHISTORYEX) lpMsgHistoryExAddress of array of 'n' ZFMSGHISTORYEX structures, where 'n' is the value given by the MaxEntries parameter

Description

This routine gets a list of the transmission history entries in the CONTROL file for a given message, giving the information about transmission attempts (result, connection time etc).

If the number of entries in the list exceeds the MaxEntries parameter, then the routine returns information about the first MaxEntries entries, but sets the IpNumEntries parameter to the total number of entries in

```
188
```

Zetafax 2012 API Help

the list. Be careful therefore to only read the lesser of (MaxEntries) and (IpNumEntries) elements of the array on return. Calling the routine with MaxEntries set to 0 will just return a count of the number of entries.

The fAllEvents flag can be used to specify whether all dial and transmission attempts should be included, or just the final status. If only the final status for a given addressee is required then the function can be called with the fAllEvents flag set to FALSE (0), and a single ZFMSGHISTORY buffer (MaxEntries = 1).

The routine opens and reads the CONTROL file for the message. This is the file which is updated by the Zetafax server while the message is in its queue. It is therefore necessary to protect against calling this routine too frequently while the entry is in the server queue - this can be done by using the ZfxCheckNewMsgStatus and ZfxGetMsgInfoEx routines to wait until the message has completed before calling this routine.

Return value

The routine returns 0 if successful, otherwise one of the following: ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_CONTROL_FILE_OPEN_ERROR ZFERR_CONTROL_FILE_ERROR ZFERR_CONTROL_FILE_INVALID

Example

```
#include <stdio.h>
#include <zfapi.h>
 . . .
#define LIST_SIZE 20
ZFMSGHISTORYEX aMsgHistoryEx[LIST_SIZE];
Err = ZfxGetMsgHistoryEx(hSession, ZFDIR_OUT, "~SEND000", 1, TRUE, LIST_SIZE,
&NumEntries, sizeof(ZFMSGHISTORYEX), MsgHistoryEx);
if (Err != 0)
ł
       return;
 }
if (NumEntries > LIST_SIZE)
       printf("Total messages %d\n", NumEntries);
       printf("Displaying first %d\n", LIST_SIZE);
 }
for (Entry = 0, Tries = 1; Entry < min(NumEntries, LIST_SIZE); Entry++)
 ł
        switch(aMsgHistoryEx[Entry]->EventType)
       {
              case ZFEVENT_TRIED:
                    Tries++;
                    printf("Tried unsuccessfully\n");
              break;
              case ZFEVENT_SENT_OK:
                     Tries++;
                     printf("Sent OK on attempt %d\n", Tries);
                     printf("Connect time %d secs\n", aMsgHistory[Event].ConnectSecs);
              break;
              case ZFEVENT_SENT_ERROR:
                    Tries++;
```

```
printf("Failed after %d attempts\n", Tries);
    printf("Pages sent %d\n", aMsgHistory[Event].Pages);
break;
default: /* ignore other events */
break;
```

Related topics Alphabetical reference Function error returns and reference

}

}

ZfxGetMsgInfo

Get information about single message.

Syntax

ZFERR FAR ZfxGetMsgInfo(ZFSESSIONHANDLE hSession, ZFMSGDIR MsgDir, char FAR *lpszBody, ZFMSGINFO FAR *lpMsgInfo)

Parameters

Parameter hSession	Description API session handle, as returned by ZfxAPIInit call MsgDirMessage type - ZFDIR_OUT for sent messages, or ZFDIR_IN for
lpszBody	received messages Message body name - NULL to delete all messages for this user IpMsgInfoAddress of a single ZFMSGINFO structure, which is filled with the details of the message (status etc) on return.

Description

This routine gets information about a message in the user's OUT or IN directories. Note that if the status of several messages is required the ZfxGetMsgList function should be used instead, as this is more efficient than several calls to this routine.

NOTE - this function is supplied for compatibility with version 5 of the Zetafax API only. Version 6 API applications should use ZfxGetMsgInfoEx.

Return value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_INFO_OPEN_FILE_ERROR ZFERR_INFO_FILE_ERROR ZFERR_INFO_FILE_INVALID ZFERR_UNKNOWN_MESSAGE

Example

```
#include <stdio.h>
#include <stdio.h>
#include <zfapi.h>
...
ZFMSGINFO MsgInfo;
if (ZfxGetMsgInfo(hSession, ZFDIR_OUT, "~XSND000", &MsgInfo) == 0
&& (MsgInfo.Status == ZFMSG_OK || MsgInfo.Status == ZFMSG_FAILED)
{
```

equisys ZETA/AX*

C language API	191

/* ok to delete message */

Related topics <u>Alphabetical reference</u> <u>Function error returns and reference</u>

}

equisys ZETA/AX[®]

ZfxGetMsgInfoEx

Get information about single message.

Syntax

ZFERR FAR ZfxGetMsgInfoEx(ZFSESSIONHANDLE hSession, ZFMSGDIR MsgDir, char FAR *lpszBody, short MsgInfoExSize, ZFMSGINFOEX FAR *lpMsgInfoEx)

Parameters

Parameter hSession	Description API session handle, as returned by ZfxAPIInit call MsgDirMessage type - ZFDIR_OUT for sent messages, or ZFDIR IN for received
lpszBody	messages Body of message file to retrieve MsgInfoExSizeSize of the ZFMSGINFOEX structure. Should be set to sizeof (ZFMSGINFOEX)
lpMsgInfoEx	Address of a single ZFMSGINFOEX structure, which is filled with the details of the message (status, comment, subject etc) on return.

Description

This routine gets information about a message in the user's OUT or IN directories. Note that if the status of several messages is required the ZfxGetMsgListEx function should be used instead, as this is more efficient than several calls to this routine.

Return value

The routine returns 0 if successful, otherwise one of the following: ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_INFO_OPEN_FILE_ERROR ZFERR_INFO_FILE_ERROR ZFERR_INFO_FILE_INVALID ZFERR_UNKNOWN_MESSAGE

Example

```
#include <stdio.h>
#include <stdio.h>
#include <zfapi.h>
...
ZFMSGINFOEX MsgInfoEx;
if (ZfxGetMsgInfoEx(hSession, ZFDIR_OUT, "~XSND000", sizeof(ZFMSGINFOEX), &MsgInfoEx)
== 0
    && (MsgInfoEx.Status == ZFMSG_OK || MsgInfoEx.Status == ZFMSG_FAILED))
{
```

C language API	193

/* ok to delete message */

Related topics <u>Alphabetical reference</u> <u>Function error returns and reference</u>

}



ZfxGetMsgList

Get status of all messages for user.

Syntax

ZFERR FAR ZfxGetMsgList(ZFSESSIONHANDLE hSession, ZFMSGDIR MsgDir, short MaxEntries, short FAR *lpNumEntries, ZFMSGINFO FAR *lpMsgInfo)

Parameters

Parameter hSession	Description API session handle, as returned by ZfxAPIInit call MsgDirMessage type - ZFDIR_OUT for sent messages, or ZFDIR_IN for received messages
MaxEntries	Maximum number of entries to be returned (ie number of elements in the arrays which follow) lpNumEntriesAddress of short integer variable used to return the number of events in the file. Note that the returned value may be larger than the value given for MaxEntries if the buffer was not large enough for all entries.
lpMsgInfo	Address of array of 'n' ZFMSGINFO structures, where 'n' is the value given by the MaxEntries parameter.

Description

This routine gets a list of the entries in the OUT or IN window list for this user, together with information about each one (current status, comment etc). If the program wants to find the status of just one message it is more efficient to call the ZfxGetMsgInfo routine.

If the number of entries in the list exceeds the MaxEntries parameter, then the routine returns information about the first MaxEntries entries, but sets the lpNumEntries parameter to the total number of entries in the list. Be careful therefore to only read the lesser of (MaxEntries) and (lpNumEntries) elements of the array on return. Calling the routine with MaxEntries set to 0 will just return a count of the number of entries.

Entries are added by selecting Send (File menu) in the Zetafax client, by calling the ZfxSendMsgEx routine, or when a new message is received. Entries are removed by selecting Save (File menu) or Delete (File menu) in the Zetafax client or calling ZfxDeleteMsg. A message may also be removed when it completes if it has the "delete on completion" option set, or for an incoming message if it is routed to another user or to an e-mail InBox.

The ZfxCheckNewMsgStatus routine should be used in conjunction with this call if repeatedly checking the status of messages, to prevent reading the INFO file unnecessarily.

 ${\bf NOTE}$ - this function is supplied for compatibility with version 5 of the Zetafax API only. Version 6 API applications should use ZfxGetMsgListEx .

Return value

```
The routine returns 0 if successful, otherwise one of the following:
ZFERR_NOT_INITIALISED
ZFERR_INVALID_PARAMETERS
ZFERR_INFO_FILE_OPEN_ERROR
ZFERR_INFO_FILE_ERROR
ZFERR_INFO_FILE_INVALID
Example
#include <stdio.h>
#include <zfapi.h>
 . . .
#define LIST_SIZE 20
ZFMSGINFO aMsgInfo[LIST_SIZE];
Err = ZfxGetMsgList(hSession, ZFDIR_OUT, LIST_SIZE, &NumEntries, aMsgInfo);
if (Err != 0)
{
       return;
}
if (NumEntries > LIST_SIZE)
{
       printf("Total messages %d\n", NumEntries);
       printf("Displaying first %d\n", LIST_SIZE);
}
for (Entry = 0; Entry < min(NumEntries, LIST_SIZE); Entry++)</pre>
 {
       printf("Entry %d : %s, status %d\n", Entry, MsgInfo[Entry].szBody, MsgInfo
[Entry].Status);
}
Related topics
```

Alphabetical reference Function error returns and reference



ZfxGetMsgListEx

Get status of all messages for user.

Syntax

ZFERR FAR ZfxGetMsgListEx(ZFSESSIONHANDLE hSession, ZFMSGDIR MsgDir, short MaxEntries, short FAR *lpNumEntries, short MsgInfoExSize, ZFMSGINFOEX FAR *lpMsgInfoEx)

Parameters

Parameter	Description
hSession	API session handle, as returned by ZfxAPIInit call MsqDirMessage
	type - ZFDIR_OUT for sent
	messages, or ZFDIR_IN for
MaxEntries	received messages Maximum number of entries to be
haxenales	returned (ie number of elements
	in the arrays which follow)
	lpNumEntriesAddress of short
	integer variable used to return the
	number of events in the file. Note
	that the returned value may be larger than the value given for
	MaxEntries if the buffer was not
	large enough for all entries.
MsgInfoExSize	Size of the ZFMSGINFOEX
- 5	structure, as given by sizeof
	(ZFMSGINFOEX).
lpMsgInfoEx	Address of array of 'n'
	ZFMSGINFOEX structures, where
	'n' is the value given by the
	MaxEntries parameter.

Description

This routine gets a list of the entries in the OUT or IN window list for this user, together with information about each one (current status, comment, subject etc). If the program wants to find the status of just one message it is more efficient to call the ZfxGetMsgInfoEx routine.

If the number of entries in the list exceeds the MaxEntries parameter, then the routine returns information about the first MaxEntries entries, but sets the lpNumEntries parameter to the total number of entries in the list. Be careful therefore to only read the lesser of (MaxEntries) and (lpNumEntries) elements of the array on return. Calling the routine with MaxEntries set to 0 will just return a count of the number of entries.

Entries are added by selecting Send (File menu) in the Zetafax client, by calling the ZfxSendMsgEx routine, or when a new message is received. Entries are removed by selecting Save (File menu) or Delete (File menu) in the Zetafax client or calling ZfxDeleteMsg. A message may also be removed when it completes if it has the "delete on completion" option set, or for an incoming message if it is routed to another user or to an e-mail InBox.

The ZfxCheckNewMsgStatus routine should be used in conjunction with this call if repeatedly checking the status of messages, to prevent reading the INFO file unnecessarily.

Return value

```
The routine returns 0 if successful, otherwise one of the following:
ZFERR_NOT_INITIALISED
ZFERR_INVALID_PARAMETERS
ZFERR_INFO_FILE_OPEN_ERROR
ZFERR_INFO_FILE_ERROR
ZFERR_INFO_FILE_INVALID
```

Example

```
#include <stdio.h>
#include <zfapi.h>
. . .
#define LIST_SIZE 20
ZFMSGINFOEX aMsgInfoEx[LIST_SIZE];
Err = ZfxGetMsgListEx(hSession, ZFDIR_OUT, LIST_SIZE, &NumEntries, sizeof(ZFMSGINFOEX),
aMsgInfoEx);
if (Err != 0)
 {
      return;
 }
if (NumEntries > LIST_SIZE)
 {
       printf("Total messages %d\n", NumEntries);
       printf("Displaying first %d\n", LIST_SIZE);
 }
for (Entry = 0; Entry < min(NumEntries, LIST_SIZE); Entry++)</pre>
 {
      printf("Entry %d : %s, status %d\n", Entry, MsgInfoEx[Entry].szBody, MsgInfoEx
[Entry].Status);
 }
Related topics
```

Alphabetical reference Function error returns and reference

ZfxGetServerStatus

Get information about the server.

Syntax

ZFERR FAR ZfxGetServerStatus(ZFSESSIONHANDLE hSession, short ServerInfoSize, ZFSERVERINFO FAR *lpServerInfo short MaxDevices, short FAR *lpNumDevices, short DeviceInfoSize, ZFDEVICEINFO FAR *lpDeviceInfo)

Parameters

Parameter hSession	Description API session handle, as returned by
	ZfxAPIInit call ServerInfoSizeSize of structure - should be set to size of
	(ZFSERVERINFO) lpServerInfoAddress of a ZFSERVERINFO structure used to return
	status information for the server
MaxDevices	Maximum number of device entries to be
	returned (ie number of elements in the
	DeviceInfo array)lpNumDevicesAddress of
	short integer variable used to return the
	number of events in the file. Note that the
	returned value may be larger than the value
	given for MaxDevices if the buffer was not
	large enough for all entries.
DeviceInfoSize	Size of structure - should be set to sizeof
	(ZFDEVICEINFO)
lpDeviceInfo	Address of array of 'n' ZFDEVICEINFO
	structures, where 'n' is the value given by
	the MaxDevices parameter.

Description

This routine gets the current status of the server (number of entries in queues etc), and of each device.

If the number of devices configured exceeds the MaxDevices parameter, then the routine returns information about the first MaxDevices devices, but sets the lpNumDevices parameter to the total number of devices in the list. Be careful therefore to only read the lesser of (MaxDevices) and (lpNumDevices) elements of the array on return. Calling the routine with MaxDevices set to 0 will just return a count of the number of devices.

NOTE - this function is supplied for compatibility with version 5 of the Zetafax API only. Version 6 API applications should use ZfxGetServerStatusEx.

Return value

The routine returns 0 if successful, otherwise one of the following: ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_SERVER_NOT_RUNNING ZFERR_FILE_OPEN_ERROR ZFERR_FILE_ERROR ZFERR_CANT_SUBMIT_REQUEST

Example

```
#include <stdio.h>
#include <zfapi.h>
. . .
#define LIST_SIZE 20
ZFSERVERINFO ServerInfo;
ZFDEVICEINFO aDeviceInfo[LIST_SIZE];
Err = ZfGetServerStatus(hSession, sizeof(ZFSERVERINFO), &ServerInfo,
LIST_SIZE, &NumDevices, sizeof(ZFDEVICEINFO), aDeviceInfo);
if (Err == 0)
 {
       printf("Items waiting for device = %d\n", ServerInfo.QueueWaitingDevice);
       if (NumDevices >= 1 && aDeviceInfo[0].szUser[0] != '\0')
       {
              printf("First device is processing %s:%s", aDeviceInfo[0].szUser,
aDeviceInfo[0].szMsgBody);
      }
 }
Related topics
```

Alphabetical reference Function error returns and reference

ZfxGetServerStatusEx

Get information about the server.

Syntax

ZFERR FAR ZfxGetServerStatusEx(ZFSESSIONHANDLE hSession, short ServerStatusExSize, ZFSERVERSTATUSEX FAR *lpServerStatusEx)

Parameters

Parameter	Description
hSession	API session handle, as returned by
	ZfxAPIInit call
	ServerStatusExSizeSize of structure -
	should be set to size of
	(ZFSERVERSTATUSEX)
lpServerStatusEx	Address of a ZFSERVERSTATUSEX
	structure used to return status
	information for the server

Description

This routine gets the current status of the server (number of entries in queues etc), of each device, and of each link to a remote server.

If the number of devices configured exceeds the lpServerStatusEx->MaxDevices parameter, then theroutine returns information about the firstlpServerStatusEx->MaxDevices devices, but sets the lpServerStatusEx->lpNumDevices parameter to the total number of devices in the list. Be careful therefore to onlyread the lesserof (lpServerStatusEx->MaxDevices) and (lpServerStatusEx->lpNumDevices) elements of the array on return. Calling theroutine with lpServerStatusEx->MaxDevices set to 0 will just return a count of the number of devices. The same logic also applies to the useof lpServerStatusEx->MaxLinks andlpServerStatusEx->lpNumLinks.

Return value

The routine returns 0 if successful, otherwise one of the following: ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_SERVER_NOT_RUNNING ZFERR_FILE_OPEN_ERROR ZFERR_FILE_ERROR ZFERR_CANT_SUBMIT_REQUEST

Example

```
#include <stdio.h>
#include <zfapi.h>
...
#define DEV_LIST_SIZE 20
#define LINK_LIST_SIZE 30
```

ZFSERVERSTATUSEX ServerStatus; ZFSERVERINFOEX ServerInfo; ZFDEVICEINFOEX aDeviceInfo[DEV_LIST_SIZE]; ZFLINKINFOEX aLinkInfo[LINK_LIST_SIZE]; equisys ZETA/AX*

```
short NumDevices;
short NumLinks;
/* initialise required fields */
memset(&ServerStatus, 0, sizeof(ServerStatus));
ServerStatus.ServerInfoExSize = sizeof(ZFSERVERINFOEX);
ServerStatus.lpServerInfoEx = &ServerInfo;
ServerStatus.MaxDevices = DEV_LIST_SIZE;
ServerStatus.lpNumDevices = &NumDevices;
ServerStatus.DeviceInfoExSize = sizeof(ZFDEVICEINFOEX);
ServerStatus.lpDeviceInfoEx = aDeviceInfo;
ServerStatus.MaxLinks = LINK_LIST_SIZE;
ServerStatus.lpNumLinks = &NumLinks;
ServerStatus.LinkInfoExSize = sizeof(ZFLINKINFOEX);
ServerStatus.lpLinkInfoEx = aLinkInfo;
Err = ZfxGetServerStatusEx(hSession, sizeof(ZFSERVERSTATUSEX), &ServerStatus);
if (Err == 0)
 {
       printf("Items waiting for device = %d\n", ServerInfoEx.QueueWaitingDevice);
       if (NumDevices >= 1 && aDeviceInfo[0].szUser[0] != '\0')
       {
             printf("Device 1 processing %s:%s", aDeviceInfo[0].szUser, aDeviceInfo[0
].szMsgBody);
      }
       if (NumLinks >= 1)
       ł
      printf("%d faxes sent OK via '%s'", aLinkInfo[0].NumSentOK, aLinkInfo[0].
szRemoteServer);
       }
 }
Related topics
Alphabetical reference
```

Function error returns and reference

ZfxGetSystemArea

Get location of system file directory.

Syntax

ZFERR FAR ZfxGetSystemArea(ZFSESSIONHANDLE hSession, char FAR *lpszBuffer, short BufLen)

Parameters

Parameter hSession	Description API session handle, as returned by ZfxAPIInit callpszBufferAddress of buffer used to return the full path of the directory, including a terminating
BufLen	backslash ('\') and NULL. Size of the buffer (including space for the terminating NULL)

Description

This routine returns the full path name of the base directory used for storing system shared files, with a backslash added to the end (eg "S:\ZFAX\SYSTEM\"). The terminating backslash means that a valid path can be formed by appending a file name to this string. This should not normally be required by API programs.

Return value

The routine returns 0 if successful, otherwise one of the following: ZFERR_NOT_INITIALISED ZFERR_BUFFER_TOO_SMALL

Example

```
#include <stdio.h>
#include <zfapi.h>
...
szPath[256];
if (ZfxGetSystemArea(hSession, szPath, sizeof(szPath)) == 0) { ... }
```



ZfxGetUserArea

Get location of user's base directory.

Syntax

ZFERR FAR ZfxGetUserArea(ZFSESSIONHANDLE hSession, char FAR *lpszBuffer, short BufLen)

Parameters

Parameter hSession	Description API session handle, as returned by ZfxAPIInit callpszBufferAddress of buffer used to return the full path of the directory,
BufLen	including a terminating backslash ('\') and NULL. Size of the buffer (including space for the terminating NULL)

Description

This routine returns the full path name of the user's base directory , with a backslash added to the end (eg "S:\ZFAX\USERS\FRED\"). The terminating backslash means that a valid path can be formed by appending a file name to this string. The directory should not normally be required by the API.

Return value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_NOT_INITIALISED ZFERR_BUFFER_TOO_SMALL

Example

```
#include <stdio.h>
#include <zfapi.h>
...
szPath[256];
if (ZfxGetUserArea(hSession, szPath, sizeof(szPath)) == 0) { ... }
```

equisys ZETA/AX[®]

ZfxGetUserCoversheet

Get user's default coversheet.

Syntax

ZFERR FAR ZfxGetUserCoversheet(ZFSESSIONHANDLE hSession, char FAR *lpszBuffer, short BufLen)

Parameters

Parameter	Description
hSession	API session handle, as returned by
	ZfxAPIInit calllpszBufferAddress
	of buffer used to return the full
	path of the directory, including a
	terminating backslash ('\') and
	NULL.
BufLen	Size of the buffer (including space
	for the terminating NULL)

Description

Each user in Zetafax can set their own default setting for the coversheet they want to use. This routine returns the name of their default coversheet, or a null string if their default setting is for no coversheet to be sent.

The routine need only be called if the program wants to perform specific processing on the coversheet name (for example, overriding it if blank), as the default will automatically be used if the "Coversheet:" line is omitted from a SUBMIT file.

The maximum length of coversheet names equal to ${\sf ZFMSG_COVERSHEET_LEN}$ (excluding space for the terminating NULL).

Return value

The routine returns 0 if successful, otherwise one of the following:

```
ZFERR_NOT_INITIALISED
ZFERR_BUFFER_TOO_SMALL
```

Example

```
#include <stdio.h>
#include <stdio.h>
#include <zfapi.h>
...
szCoversheet[ZFMSG_COVERSHEET_LEN+1];

if (ZfxGetUserCoversheet(hSession, szCoversheet, sizeof(szCoversheet)) != 0
|| szCoversheet[0] == '\0') /*if default is no coversheet */
{
    /* force a coversheet to be used */
    strcpy(szCoversheet, "COVSHEET");
}
```

C language API	205

equisys ZETA/AX[®]

ZfxGetUserFromname

Get user's default sender name.

Syntax

ZFERR FAR ZfxGetUserFromname(ZFSESSIONHANDLE hSession, char FAR *lpszBuffer, short BufLen)

Parameters

Parameter hSession	Description API session handle, as returned by ZfxAPIInit calllpszBufferAddress of
BufLen	buffer used to return the full path of the directory, including a terminating backslash ('\') and NULL. Size of the buffer (including space for the terminating NULL)

Description

This routine returns the default setting for the sender name for messages submitted by this user (usually their full name). When a new user is created the sender name is set to the full name entered in the Zetafax Configuration program, but the user can then change it using the Zetafax client. Note that editing an existing user in the Setup program does not change the sender name.

The routine need only be called if the program wants to perform specific processing on the name (for example, overriding it if blank), as the default will automatically be used if the "From:" line is omitted from a SUBMIT file.

Sender names have a maximum length of ZFMSG_FULLNAME_LEN (excluding space for the terminating NULL).

Return Value

The routine returns 0 if successful, otherwise one of the following:

```
ZFERR_NOT_INITIALISED
ZFERR_BUFFER_TOO_SMALL
```

Example

Related topics

C language API	207

Г

Alphabetical reference Function error returns and reference



ZfxGetUserInDir

Get location of user's IN directory.

Syntax

ZFERR FAR ZfxGetUserInDir(ZFSESSIONHANDLE hSession, char FAR *lpszBuffer, short BufLen)

Parameters

)

Description

This routine returns the full path name of the user's OUT directory, with a backslash added (eg "S: ZFAXUSERSFREDZ-OUT"). The terminating backslash means that a valid path can be formed by appending a file name to this string.

Return value

The routine returns 0 if successful, otherwise one of the following: ZFERR_NOT_INITIALISED ZFERR_BUFFER_TOO_SMALL

Example

```
#include <stdio.h>
#include <zfapi.h>
...
szPath[256];
if (ZfxGetUserInDir(hSession, szPath, sizeof(szPath)) == 0)
{
...
}
```



ZfxHoldMsg

Request server to suspend processing of message.

Syntax

ZFERR FAR ZfxHoldMsg(ZFSESSIONHANDLE hSession, ZFMSGDIR MsgDir, char FAR *lpszBody)

Parameters

Description
API session handle, as returned by ZfxAPI
MsgDirMessage type (ZFDIR_OUT)
Base name of message file

Description

This routine is called to stop the server processing a message after it has been submitted using ZfxSendMsgEx. The routine sends a request to the Zetafax server, which processes it asynchronously.

Held messages remain in the queue in their original position until released or deleted. Any transmissions in progress when the hold request is received will not be interrupted, but no further preparation will take place and the message will not be submitted to any new devices for sending. Normal processing is resumed by calling the ZfxReleaseMsg function.

Return value

The routine returns 0 if successful, otherwise one of the following:

```
ZFERR_NOT_INITIALISED
ZFERR_INVALID_PARAMETERS
ZFERR_UNKNOWN_MESSAGE
ZFERR_SERVER_NOT_RUNNING
ZFERR_CANNOT_SUBMIT_REQUEST
```

Example

```
#include <stdio.h>
#include <zfapi.h>
...
if (ZfxHoldMsg(hSession, ZFDIR_OUT, "~XSND000") == 0)
{
    printf("Message hold request sent\n");
    /* Processing not stopped until status */
    /* changes to ZFMSG_HELD */
    ...
}
```



ZfxMarkMsgAsRead

Marks message as 'read' (changes the user status of the message).

Syntax

ZFERR FAR ZfxMarkMsgAsRead(ZFSESSIONHANDLE hSession, ZFMSGDIR MsgDir, char FAR *lpszBody)

Parameters

ParameterDescriptionHsessionAPI sessionreturned by

API session handle, as returned by ZfxAPIInit call MsgDir Message type (ZFDIR_OUT)LpszBodyBase name of message file

Description

This routine is called to mark a specified message as 'read'. It updates the user staus of the message in the control files so does not need to send any requests to the Zetafax Server.

Return value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_UNKNOWN_MESSAGE ZFERR_SERVER_NOT_RUNNING

Example

```
#include <stdio.h>
#include <zfapi.h>
...
if (ZfxMarkMsgAsRead(hSession, ZFDIR_OUT, "~XSND000") == 0)
{
    printf("Message marked as read\n");
    /* viewing the user's message */
    /*in the client would now show */
    /* the message as being read */
    ...
}
```



ZfxReleaseMsg

Request server to resume processing of message.

Syntax

ZFERR FAR ZfxReleaseMsg(SESSIONHANDLE hSession, ZFMSGDIR MsgDir, char FAR *lpszBody)

Parameters

ParameterDescriptionhSessionAPI session handle, as returned by
ZfxAPIInit calIMsgDirMessage type (ZFDIR_OUT)IpszBodyBase name of message file

Description

This routine is called to resume the server processing a message that has been suspended with ZfxHoldMsg . The routine sends a request to the Zetafax server, which processes it asynchronously.

Return value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_UNKNOWN_MESSAGE ZFERR_SERVER_NOT_RUNNING ZFERR_CANNOT_SUBMIT_REQUEST

Example

```
#include <stdio.h>
#include <zfapi.h>
...
if (ZfxReleaseMsg(hSession, ZFDIR_OUT, "~XSND000") == 0)
{
    printf("Message release request sent\n");
}
```



ZfxRestartServer

Restart the Zetafax server.

Syntax

ZFERR FAR ZfxRestartServer(ZFSESSIONHANDLE hSession, SHORT fReserved)

Parameters

 Parameter
 Description

 hSession
 API session handle, as returned by by ZfxAPIInit call

 fReserved
 Reserved - set to FALSE (0)

Description

This routine requests the Zetafax server to restart if already running. This is equivalent to ZfxStopServer followed by ZfxStartServer, but can be called from any machine (unlike ZfxStartServer which must be called on the fax server PC).

When the server programs restart, they re-read the initialization files and settings. ZfxRestartServer can therefore be used after making changes to the server settings, such as adding or removing fax devices. Note however that restarting the server will abort any faxes currently being sent or received.

Return value

The routine returns 0 if successful, otherwise one of the following:

```
ZFERR_NOT_INITIALISED
ZFERR_SERVER_NOT_RUNNING
```

Example

```
#include <stdio.h>
#include <zfapi.h>
...
Err = ZfxRestartServer(hSession, FALSE);
if (Err == 0)
{
    printf("Server restarting\n"); }
else
{
    printf("Unable to restart server\n");
}
```


ZfxRushMsg and ZfxRushMsgEx

Request server to stop processing message.

Syntax

ZFERR FAR ZfxRushMsg(ZFSESSIONHANDLE hSession, ZFMSGDIR MsgDir, char FAR *lpszBody) ZFERR FAR ZfxRushMsgEx(ZFSESSIONHANDLE hSession, ZFMSGDIR MsgDir, char FAR *lpszBody, char FAR *lpszMsgID)

Parameters

Parameter	Description
Hsession	API session handle, as
	returned by ZfxAPIInit call
	MsgDir Message type
	(ZFDIR_OUT)
lpszBody	Base name of message file
lpszMsgID	Message ID

Description

These routines are called to request the server rush the processing a message after it has been submitted using ZfxSendMsgEx. The routine sends a request to the Zetafax server, which processes it asynchronously.

Return value

The routine returns 0 if successful, otherwise one of the following: ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_UNKNOWN_MESSAGE ZFERR_SERVER_NOT_RUNNING ZFERR_CANNOT_SUBMIT_REQUEST

Example

```
#include <stdio.h>
#include <stdio.h>
#include <zfapi.h>
...

if (ZfxRushMsg(hSession, ZFDIR_OUT, "~XSND000") == 0)
{
    printf("Message rushed");
    /* server should now speed up the */
    /* processing of the message */
    /* now wait for status to change to */
    /* ZFMSG_OK or ZFMSG_FAILED before */
    /* deleting the message */
    ...
}
```

Related topics Alphabetical reference Function error returns and reference



ZfxSendMsg

Submit message to fax server for sending.

Syntax

ZFERR FAR ZfxSendMsg(ZFSESSIONHANDLE hSession, char FAR *lpszBody, char FAR *lpszDataExtn, char FAR *lpszComment)

Parameters

Parameter	Description
hSession	API session handle, as
	returned by ZfxAPIInit call
lpszBody	Body name of control file and
	data
	filelpszDataExtnExtension of
	data file corresponding to the
	data format
lpszComment	Descriptive comment (of
	maximum length
	ZFMSG_COMMENT_LENGTH).
	This is the comment that
	appears on the Zetafax client display OUT directory list.
	• •

Description

This routine makes an entry for a new message in the user's OUT directory INFO file then sends a message to the Zetafax server asking it to queue the message for sending.

The caller should first create two files in the users OUT directory (as given by the ZfxGetUserOutDir function). These are the control file (with extension ".CTL"), and the data file (with an extension corresponding to the data file format, as specified in File System Structure section above. The two files should have the same body name, which will usually have been determined by calling the ZfxCreateAutoFileroutine.

Note that once a message has been submitted to the fax server for processing, the server will periodically open the control file to change the status lines or append message history and status information to the file. It is recommended that application programs avoid opening the control file until the status of the message changes to ZFMSG_OK or ZFMSG_FAILED, at which point the server has completed processing of the message. However, if the program requires to read the file during this time then it must not be kept open for more than 2 seconds, otherwise status updates may be lost.

NOTE - this function is supplied for compatibility with version 5 of the Zetafax API only. Version 6 API applications should use ZfxSendMsgEx.

Return value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_SERVER_NOT_RUNNING ZFERR_FILE_NOT_FOUND ZFERR_MESSAGE_ALREADY_EXISTS 216 Zetafax 2012 API Help

ZFERR_INFO_FILE_OPEN_ERROR ZFERR_INFO_FILE_ERROR ZFERR_INFO_FILE_INVALID ZFERR_CANNOT_SUBMIT_REQUEST

Example

```
#include <stdio.h>
#include <zfapi.h>
...
/* create ~XSND000.CTL and ~XSND000.TXT */
...
if (ZfxSendMsg(hSession, "~XSND000", "TXT", "To: Sam Smith") == 0)
{
    printf("Submitted to Zetafax server\n");}
else
{
    /* delete the two files */
    ...
}
```


ZfxSendMsgEx

Submit message to fax server for sending.

Syntax

ZFERR FAR ZfxSendMsgEx(ZFSESSIONHANDLE hSession, char FAR *lpszDataExtn, short MsgInfoExSize, ZFMSGINFOEX lpMsgInfoEx)

Parameters

Parameter	Description
hSession	API session handle, as returned by ZfxAPIInit call
lpszDataExtn	Extension of data file corresponding to the data
	format
MsgInfoExSize	Size of the ZFMSGINFOEX
	structure, as returned by
	sizeof(ZFMSGINFOEX).
lpMsgInfoEx	Address of a single
	ZFMSGINFOEX structure,
	containing the body, comment and subject of the message to be submitted.

Description

This routine makes an entry for a new message in the user's OUT directory INFO file then sends a message to the Zetafax server asking it to queue the message for sending.

The caller should first create two files in the users OUT directory (as given by the ZfxGetUserOutDir function). These are the control file (with extension ".CTL"), and the data file (with an extension corresponding to the data file format, as specified in File System Structure section above. The two files should have the same body name, which will usually have been determined by calling the ZfxCreateAutoFileroutine.

Note that once a message has been submitted to the fax server for processing, the server will periodically open the control file to change the status lines or append message history and status information to the file. It is recommended that application programs avoid opening the control file until the status of the message changes to ZFMSG_OK or ZFMSG_FAILED, at which point the server has completed processing of the message. However, if the program requires to read the file during this time then it must not be kept open for more than 2 seconds, otherwise status updates may be lost.

Return value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_SERVER_NOT_RUNNING ZFERR_FILE_NOT_FOUND ZFERR_MESSAGE_ALREADY_EXISTS ZFERR_INFO_FILE_OPEN_ERROR ZFERR_INFO_FILE_ERROR ZFERR_INFO_FILE_INVALID ZFERR_CANNOT_SUBMIT_REQUEST

Example

```
#include <stdio.h>
#include <zfapi.h>
...
ZFMSGINFOEX MsgInfo;
...
/* create ~XSND000.CTL and ~XSND000.TXT */
...
if (ZfxSendMsgEx(hSession, "TXT", sizeof(ZFMSGINFOEX), &MsgInfo) == 0)
{
    f("Submitted to Zetafax server\n");}
else
{
    /* delete the two files */
    ...
}
```



ZfxSendSubmitFile

Send a single SUBMIT format file.

Syntax

ZFERR FAR ZfxSendSubmitFile(ZFSESSIONHANDLE hSession, char FAR *lpszSubmitFile, char FAR *lpszPrefix, char FAR *lpszBody)

Parameters

Parameter	Description
hSession	API session handle, as returned by ZfxAPIInit call
lpszSubmitFile	Name of submit file (with path if not in current directory)lpszPrefix4 characters string giving the prefix to use when creating the control and data files.
lpszBody	Address of buffer of length ZFMSG_BODY_LEN+1 used to return the message body name if successfully submitted for sending.

Description

This routine interprets the given SUBMIT format file, creating a CONTROL file and a DATA file (in ASCII text or Epson print format). It then calls the ZfxSendMsgEx function to submit these files for sending, and if successful returns the name of the message submitted. This is the simplest method of submitting a fax using the API.

Return value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_FILE_OPEN_ERROR ZFERR_FILE_ERROR ZFERR_MESSAGE_ALREADY_EXISTS ZFERR_SERVER_NOT_RUNNING ZFERR_SUBMIT_FILE_INVALID ZFERR_INFO_FILE_OPEN_ERROR ZFERR_INFO_FILE_ERROR ZFERR_INFO_FILE_INVALID ZFERR_CANNOT_SUBMIT_REQUEST

Example

```
#include <stdio.h>
#include <zfapi.h>
...
if ((fp = fopen("XYZ.TMP", "w+b")) != NULL)
{
```

```
fputs("%%[MESSAGE]\r\n", fp);
fputs("From: Fred Smith\r\n", fp);
fputs("To: Jim Jones\r\n", fp);
fputs("Fax: 123 456 7890\r\n", fp);
fputs("%%[TEXT]\r\n", fp);
fputs("Hello Jim\r\n", fp);
fclose(fp);
Err = ZfxSendSubmitFile(hSession, "XYZ.TMP", "XSUB", szBody);
remove("XYZ.TMP");
}
if (Err == 0)
{
    printf("Submitted message %s\n", szBody);
}
```



ZfxSendSubmitFileFP

Send a single SUBMIT format file (old version).

Syntax

ZFERR FAR ZfxSendSubmitFileFP(ZFSESSIONHANDLE hSession, FILE *fpSubmit, char FAR *lpszPrefix, char FAR *lpszBody)

Parameters

Parameter	Description
hSession	API session handle, as
	returned by ZfxAPIInit call
fpSubmit	•
	, , , ,
	()
	parameter to the fopen call).
	The file pointer should be
	positioned at the start of the %
	%[MESSAGE] line.
lpszPrefix	4 characters string giving the
	prefix to use when creating the
	control and data files.
lpszBody	Address of buffer of length
. ,	ZFMSG BODY LEN+1 used to
	return the message body
	name if successfully submitted
	for sending.
fpSubmit lpszPrefix	returned by ZfxAPIInit call File pointer for SUBMIT format file, opened in binary mode with read access (eg an "rb" parameter to the fopen call). The file pointer should be positioned at the start of the % %[MESSAGE] line. 4 characters string giving the prefix to use when creating the control and data files. Address of buffer of length ZFMSG_BODY_LEN+1 used to return the message body name if successfully submitted

Description

This routine interprets the given SUBMIT format file, creating a CONTROL file and a DATA file (in ASCII text or Epson print format). It then calls the ZfxSendMsgEx function to submit these files for sending, and if successful returns the name of the message submitted. This is the simplest method of submitting a fax using the API.

The SUBMIT file must have been opened with read access - ie if the file is created by the application program first, then it should be opened with access "w+" not just "w".

NOTE - this routine is supplied for historic reasons to assist porting applications written for an older version of the API. Because of its use of file pointers is only supported in the static library version of the API, not the DLL. New programs should use the ZfxSendSubmitFile function instead.

Return value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_FILE_ERROR ZFERR_MESSAGE_ALREADY_EXISTS ZFERR_SERVER_NOT_RUNNING ZFERR_SUBMIT_FILE_INVALID ZFERR_INFO_FILE_OPEN_ERROR ZFERR_INFO_FILE_ERROR ZFERR_INFO_FILE_INVALID ZFERR_CANNOT_SUBMIT_REQUEST

Example

```
#include <stdio.h>
#include <zfapi.h>
. . .
if ((fp = fopen("XYZ.TMP", "w+b")) != NULL)
{
       fputs("%%[MESSAGE]\r\n", fp);
       fputs("From: Fred Smith\r\n", fp);
       fputs("To: Jim Jones\r\n", fp);
       fputs("Fax: 123 456 7890\r\n", fp);
      fputs("%%[TEXT]\r\n", fp);
      fputs("Hello Jim\r\n", fp);
      fseek(fp, OL, SEEK_SET);
      Err = ZfxSendSubmitFileFP(hSession, fp, "XSUB", szBody);
      fclose(fp);
      remove("XYZ.TMP");
}
if (Err == 0)
 {
       printf("Submitted message s\n", szBody);
 }
```



ZfxStartServer

Start the Zetafax server on this PC.

Syntax

ZFERR FAR ZfxStartServer(ZFSESSIONHANDLE hSession, SHORT fReserved, char FAR *lpszReserved)

Parameters

Parameter
hSessionDescriptionhSessionAPI session handle, as
returned by ZfxAPIInit callfReservedReserved - set to FALSE (0)lpszReservedReserved - set to NULL

Description

This routine starts the Zetafax server on the current PC. The PC must have been correctly configured to run the server. The server programs are started in turn. This routine returns once the server has begun starting, but the calling application should then use the ZfxCheckServer routine to determine when it has started.

Return value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_NOT_INITIALISED ZFERR_INVALID_PARAMETERS ZFERR_SERVER_RUNNING ZFERR_CANNOT_RUN_SYSTEM_MANAGER ZFERR_ERROR_STARTING_SERVER

Example

```
#include <stdio.h>
#include <zfapi.h>
...
Err = ZfxStartServer(hSession, FALSE, NULL);
if (Err == 0)
{
    printf("Server starting\n");
}
else
{
    printf("Unable to start server\n");
}
```



ZfxStopServer

Stop the Zetafax server.

Syntax

ZFERR FAR ZfxStopServer(ZFSESSIONHANDLE hSession, SHORT fReserved)

Parameters

Parameter	Description
hSession	API session handle, as
	returned by ZfxAPI
Init callfReserved	Reserved - set to FALSE (0)

Description

This routine requests the Zetafax server to stop. Note that this will abort any faxes currently being sent or received.

Return value

The routine returns 0 if successful, otherwise one of the following: ZFERR_NOT_INITIALISED ZFERR_SERVER_NOT_RUNNING

Example

```
#include <stdio.h>
#include <stdio.h>
#include <zfapi.h>
...
Err = ZfxStopServer(hSession, FALSE);

if (Err == 0)
{
    printf("Server stopping\n");
}
else
{
    printf("Unable to stop server\n");
}
```


ZfxVBSendSubmitFile

Send a single SUBMIT format file.

Syntax

ZFERR FAR ZfxVBSendSubmitFile(char FAR *lpszUsername, char FAR *lpszSubmitFile, char FAR *lpszPrefix)

Parameters

Parameter	Description
lpszUserName	Zetafax username to use
	for submitting the
	message
lpszSubmitFile	Full path and file name
	of SUBMIT format file to
	send.
lpszPrefix	4 characters string
	giving the prefix to use
	when creating the
	control and data files.

Description

This routine interprets the given SUBMIT format file, creating a CONTROL file and a DATA file (in ASCII text or Epson print format). It then calls the ZfxSendMsgEx function to submit these files for sending.

This is equivalent to calling ZfxAPIInit, ZfxSendSubmitFile and ZfxAPIClosedown. It is supplied for programs that can call functions in the DLL, but are unable to store the session handle returned by ZfxAPIInit and pass it to the other two functions - word processor macro languages and some Visual Basic applications, for example.

The ZfxAPIInit function has to do a certain amount of work to determine the system configuration and user settings, so it is more efficient when submitting multiple faxes to keep a session open (calling ZfxAPIInit once when the application starts for example) then repeatedly call ZfxSendSubmitFile. It is therefore recommended that this function is only used by programs that are unable to use ZfxSendSubmitFile .

Return value

The routine returns 0 if successful, otherwise one of the following:

ZFERR_INVALID_PARAMETERS ZFERR_NO_ZF_INIT_FILE ZFERR_INVALID_ZF_INIT_FILE ZFERR_UNKNOWN_USER ZFERR_CANNOT_LOG_ON ZFERR_FILE_OPEN_ERROR ZFERR_FILE_ERROR ZFERR_SERVER_NOT_RUNNING ZFERR_SUBMIT_FILE_INVALID ZFERR_INFO_FILE_OPEN_ERROR ZFERR_INFO_FILE_ERROR ZFERR_INFO_FILE_INVALID ZFERR_INFO_FILE_INVALID ZFERR_CANNOT_SUBMIT_REQUEST

Example

226

```
#include <stdio.h>
#include <zfapi.h>
. . .
if ((fp = fopen("XYZ.TMP", "w+b")) != NULL)
{
       fputs("%%[MESSAGE]\r\n", fp);
       fputs("From: Fred Smithr\n", fp);
       fputs("To: Jim Jones\r\n", fp);
       fputs("Fax: 123 456 7890\r\n", fp);
       fputs("%%[TEXT]\r\n", fp);
      fputs("Hello Jim\r\n", fp);
      fclose(fp);
      Err = ZfxVBSendSubmitFile("FRED", "XYZ.TMP", "XSUB");
      remove("XYZ.TMP");
      if (Err == 0)
       {
             printf("Submitted message\n");
       }
}
```



DDE commands

Applications such as word processors may communicate with the Zetafax client program directly using DDE commands. Provided adequate details have first been given using the DDE commands, when a document is "printed" using the Zetafax Windows printer driver no dialogs will be displayed and the fax or faxes will be submitted to the Zetafax server automatically.

DDE conversation

Before issuing any addressing commands, a DDE conversation must be established between the application and the Zetafax client program. The name of the DDE server is **Zetafax**, and the topic for the purposes of addressing faxes is **Addressing**.

The Zetafax client program should be put under the control of DDE by issuing a DDEControl DDE Execute call.

Addressing commands can then be issued using DDE Poke calls. Details of the commands which may be used are given below.

A message file should be created by printing using the Zetafax Windows printer driver. Alternatively an ASCII file, or a suitable Epson or TIFF file, may be copied to the spool file location used by the Zetafax client program (usually C:\WINDOWS\ZETAFAX.SPL, set by the LogArea: entry in the ZETAFAX.INI file).

The message can be submitted to the Zetafax server for sending with a Send DDE Execute call, or for preview with a Preview DDE Execute call.

Further messages can be submitted by specifying a new addressee, organization, and fax number, creating a new message file, and then issuing a Send or Preview DDE Execute call.

Note: Each of the addressing settings, such as the choice of letterhead, will remain unchanged between messages until the appropriate DDE Poke call is made to alter it. If these settings need to be reset to their default values between messages, the Zetafax client program should be released from DDE control with a DDERelease DDE Execute call and then put back under DDE control with a DDEControl DDE Execute call.

After submitting the message or messages the Zetafax client program should be released from the control of DDE by issuing a DDERelease DDE Execute call.

The DDE conversation should finally be terminated properly.

Commands

The following WM_DDE_EXECUTE commands may be issued using the Addressing topic:

Command	Description
DDEControl	Puts the Zetafax client program under DDE control for addressing.
Send	Submits a message to the Zetafax server for sending.
Preview	Submits a message to the Zetafax server for preview.
DDERelease	Releases the Zetafax client from DDE control.

Poke items

The following table lists the items that may be poked (WM_DDE_POKE) using the Addressing topic whilst the Zetafax client program is under DDE control on all Zetafax configurations:

ltem	Parameters
То	fax, recipient name, organization

Fax fax Name recipient name Organization organization

For a description of each command and its parameters see <u>SUBMIT file Message Addressing lines</u>.

With an API license the following additional items may be poked:

ltem	Parameters
From	sender name
Coversheet	coversheet
Letterhead	letterhead
Quality	quality
Priority	priority
After	time
Time	time
Header	header
Attach	files
Charge	chargecode

For a full description of each command and its parameters, see <u>SUBMIT file Message Option lines</u>.

Related topics Example DDE macros

228



Example DDE macros

Windows 98

The following Microsoft Word macro demonstrates the use of DDE commands to submit the current document to the Zetafax server for sending by fax:

Sub MAIN
REM Set up DDE control of Zetafax
Convl = DDEInitiate("Zetafax", "Addressing")
DDEExecute(Convl, "[DDEControl]")
REM Set the addressing options
DDEPoke(Convl, "To", "123 456 7890, Sam Smith, Smith and Sons")
REM Set Zetafax To the default printer And Print the document
FilePrintSetup .Printer = "Zetafax printer on ZETAFAX.SPL"
FilePrint
REM Submit the fax And release DDE control
DDEExecute(Convl, "[Send][DDERelease]")
DDETerminate(Convl)

Background printing

End Sub

Please note that this macro disables the background printing feature when printing to the Zetafax printer from within a Microsoft Word macro. This is done by adding the following line:

ToolsOptionsPrint .Background = 0

You can also re-activate background printing by adding the following line to the end of your macro:

ToolsOptionsPrint .Background = 1

Windows NT

Because Windows NT uses a different naming convention for its printer ports it is necessary to adjust the macro shown above to accommodate for this. The simplest way to do this is to record a new macro where you select your Zetafax printer. In the example above, you need to change the FilePrintSetup call to specify the spool file path which would look something like:

FilePrintSetup .Printer = "Zetafax printer on NE00:"

This is best done by recording a simple macro within Word of you selecting the Zetafax printer and copying the resulting Word Basic code to your Zetafax DDE macro.

Here is an example Word for Windows macro which submits the current document to the fax server for sending by fax under Windows NT:

```
Sub MAIN
REM Set up DDE control of Zetafax
Conv1 = DDEInitiate("Zetafax", "Addressing")
DDEExecute(Conv1, "[DDEControl]")
REM Set Zetafax To the default printer And Print the document
FilePrintSetup .Printer = "Zetafax printer on NE00:"
REM Disable background printing
```

230

Zetafax 2012 API Help

```
ToolsOptionsPrint .Background = 0
FilePrint
REM Set the addressing options
DDEPoke(Conv1, "To", "123 456 7890, Sam Smith, Smith & Sons")
DDEPoke(Conv1, "Quality", "High")
DDEPoke(Conv1, "Time", "19:00:00")
DDEPoke(Conv1, "Attach", "infopack")
REM Submit the fax And release DDE control
DDEExecute(Conv1, "[Send][DDERelease]")
DDETerminate(Conv1)
End Sub
```

Microsoft Excel

In Microsoft Excel, the DDEPoke instructions do not support a constant string as data. It must be a range address. So, instead of using the line:

DDEPoke Conv1, "From", "John Doe"

The instruction should appear as:

DDEPoke Conv1, "From", WorkSheets("Sheet1").Range("A1")

Here is an example Excel macro that will submit the current document to the fax server using addressing information contained in fields within an active worksheet.

```
Sub Macrol()
ZetaTalk = DDEInitiate( _ app:="Zetafax",_ topic:="Addressing")
Application.ActivePrinter = "Zetafax printer on NE00:"
ActiveSheet.PrintOut
DDEExecute ZetaTalk, "[DDEControl]"
Set RecipientName = Worksheets("Sheet1").Range("A1")
Set OrgName = Worksheets("Sheet1").Range("B1")
Set FaxNumber = Worksheets("Sheet1").Range("C1")
Application.DDEPoke ZetaTalk, "Name", RecipientName
Application.DDEPoke ZetaTalk, "Organisation", OrgName
Application.DDEPoke ZetaTalk, "Fax", FaxNumber
Rem Submit the fax And release DDE control
DDEExecute ZetaTalk, "[Send][DDERelease]"
DDETerminate ZetaTalk
```

End Sub



Embedded Addressing

Like many fax packages, Zetafax has a Windows printer driver. Print from a Windows application, and a dialog box will pop-up asking you where the fax is to be sent. With the API this can be automated by including options such as the fax number in the document being printed. Zetafax will pick out the embedded addressing information and act upon it.

You can use embedded addressing to broadcast faxes from a database or using a word processor mailmerge so each recipient's copy will be personalised.

The Zetafax client program allows addressing instructions to be included into documents using embedded commands:

Embedded Addressing information Option Commands Action Commands Using Embedded Addressing with Mail Merge



Embedded addressing information

The Zetafax client program allows addressing instructions to be embedded into documents using embedded commands.

Supported platforms

Embedded addressing is supported using the Zetafax Printer driver on the following operating systems:

- Windows XP
- Windows 2000
- Windows NT 4.0
- Windows 95/98

Embedded addressing is not currently supported on Microsoft Terminal Server, Windows Terminal Services or Citrix Metaframe environments.

Use without the API

Limited support for embedded addressing commands and DDE is standard in Zetafax. This guide gives details of all of the options available when the API toolkit is purchased for the product.

The concept

Word processor and other applications' documents may contain commands to indicate where a fax should be sent, together with a wide range of settings such as the time of sending, priority, resolution, coversheet and letterhead to use. If these commands are used in a document, they must be typed using one of Zetafax's own typefaces, and in the appropriate syntax - for example:

%%[Fax:123 456 7890]

When the document is "printed" using the Zetafax printer driver, the addressing commands are used by the Zetafax client program in place of the addressing dialog boxes. Provided adequate details are given, no dialog boxes will be displayed and the fax or faxes will be submitted to the fax server automatically.

Supported fonts

The Zetafax printer supports embedded addressing in Windows XP, Windows 2000, Windows NT 4.0 and Windows 95/98. When using embedded addressing commands they can be entered into a document in any available Windows font; however the embedded addressing commands must use the appropriate syntax and appear on a line of their own. Earlier versions of Zetafax under certain operating environments required the use of Zetafax specific fonts for embedded addressing.

Related topics Options commands Action commands Using embedded addressing with mail merge



Commands

Option Commands

The addressing commands are similar in syntax to entries in Submit files. They are enclosed in the special characters %%[] to distinguish them from printable text. The embedded command text does not appear on the faxes produced by Zetafax.

The following commands are available on all Zetafax configurations.

<u>To</u> <u>Fax</u> <u>Name</u> <u>Organisation</u> <u>Send</u> <u>Preview</u>

The remaining options commands are only available if the API toolkit is licensed:

From Coversheet Letterhead Quality Priority Time Header Attach Charge Discard Subject Note Delete

Related topics Embedding addressing information Using embedded addressing with mail merge



То

Syntax

%%[To: fax, recipientname, organisation]

where fax is the fax number to send the fax to, recipientname is the person the fax is addressed to, and organisation is that person's company or organisation; fax, recipientname, and organisation may each appear in double quotation marks if required.

Description

Specifies the fax number to use and the details of the recipient which are put on the fax cover sheet and at the top of each page of the fax.

Example

%%[To: 123 456 7890, Sam Smith, Smith and Sons]



Name

Syntax

%%[Name: recipientname] where recipientname is the person the fax is addressed to.

Description

A subset of and alternative to the %%[To:]; used with the %%[Fax] command.

Example

%%[Name: Sam Smith]



Fax

Syntax

%%[Fax: fax] where fax is the fax number to send the fax to.

Description

A subset of and alternative to the %%[To:] command.

Example

%%[Fax: 123 456 7890]



Organisation

Syntax

%%[Organisation: organisation]

where organisation is the recipient's company or organisation.

Description

A subset of and alternative to the %%[To:] command; used with the %%[Fax] command.

Example

%%[Organisation: Smith and Sons]



Send

Syntax

%%[SEND]

Description

Indicates that the document being printed should be split at the foot of this page and submitted as a fax. The remaining page or pages will be treated as a separate fax or faxes.

Example

%%[Send]



Preview

Syntax

%%[Preview]

Description

Indicates that the document being printed should be split at the foot of this page and submitted as a fax for preview. The remaining page or pages will be treated as a separate fax or faxes.

Example

%%[Preview]



From

Syntax

%%[FROM: sendername]

where sendername is the originator of the fax - it may appear in double quotation marks.

Description

Specifies the name which is put on the fax coversheet as the sender of the fax (cf the From: field on the Zetafax addressing dialog box).

Example

%%[From: Jim Jones]



Coversheet

Syntax

%%[COVERSHEET: coversheet]

where coversheet is the name of the file to be used to generate a coversheet for the fax (1 to 8 characters long) or blank for no coversheet - coversheet may appear in double quotation marks.

Description

Specifies what coversheet to generate for the fax onto before sending.

Example

%%[Coversheet: COVSHEET]



Quality

Syntax

%%[QUALITY: quality]

where quality is one of DRAFT, NORMAL or HIGH.

Description

Specifies the resolution to be used when sending the fax, in the same way as the Resolution button on the Zetafax client sending options dialog box. For fax, DRAFT and HIGH will normally force the fax to be sent at standard (200x100 dpi) and fine (200x200 dpi) resolutions respectively, whilst NORMAL will send at whichever resolution has been specified by the system administrator in the system initialization file.

Example

%%[Quality: NORMAL]



Letterhead

Syntax

%%[LETTERHEAD: letterhead]

where letterhead is the name of the file to be used as the letterhead (1 to 8 characters long) or blank for no letterhead - letterhead may appear in double quotation marks.

Description

Specifies what letterhead to merge the fax onto before sending.

Example

%%[Letterhead: LETTHEAD]



Priority

Syntax

%%[PRIORITY: priority]

where priority is one of URGENT, NORMAL or BACKGROUND.

Description

Specifies the priority to be used when queuing the fax, in the same way as the Priority radio button on the Zetafax client sending options dialog box.

Example

%%[Priority: NORMAL]



Time

Syntax

%%[AFTER: time] or %%[TIME: time]

where time specifies the earliest time that the message should be sent, for deferred sending. The format of the time field may be one of the following: hh:mm:ss (given time today) yy-mm-dd hh:mm:ss (date and time specified) OFFPEAK (as defined in SETUP.INI) If the time field is omitted the message is queued for sending immediately. **Description**

Specifies when the message is to be sent.

Example

%%[After: 99-03-01 18:00:00]



Header

Syntax

%%[HEADER: header] where header is one or more of No, To, Fr, Dt and Ti.

Description

Specifies the header to appear at the top of each page of the fax, in the same way as the Header radio button on the Zetafax client sending options dialog box. No page numbering (n/N) To name of recipient Fr name of sender Da date Ti time

Example

%%[Header: NoToFrDt]



Attach

Syntax

%%[ATTACH: files]

where files is a comma separated list of graphics files to attach to the fax.

Description

Specifies the attachment files in the user's private graphics directory (Z-GRAPH) or in the system graphics directory, in the same way as the Attach radio button on the Zetafax client sending options dialog box.

Example

%%[Attach: INFOPACK, PRICES]



Charge

Syntax

%%[CHARGE: chargecode]

where chargecode is the charge code to be used for the fax

Description

Specifies the charge code to be used when queuing the fax, in the same way as the Charge combo box on the Zetafax client addressing dialog box.

Example

%%[Charge: SALES]



Discard

Syntax

%%[DISCARD]

Description

Specifies that this page will not be faxed. This command allows you to put all the embedded addressing commands on to one page and not have to worry about upsetting the formatting of the actual fax. Please note that this is not be available on Windows 95/98.

Example

%%[Discard]



Subject

Syntax

%%[SUBJECT: subjectline]

where subjectline is the subject of the fax.

Description

Specifies the subject field for the fax which can appear on the coversheet.

Example

%%[Subject: About the new sales figues]



Note

Syntax

%%[NOTE: notetext] where notetext is the text to appear in the coversheet note field.

Description

Specifies the note field text that can appear on the coversheet.

Exam ple

%%[Note: Please find attached the price list]



Delete

Syntax

%% [DELETE: delete] where delete is YES, OK or NO.

Description

Specifies whether the fax should be deleted after sending. If delete is YES then the faxes are deleted after they have been sent (successful or failed). If delete is OK then the faxes are deleted after they have been sent successfully. If delete is NO then the faxes are **not** deleted after they have been sent (a blank line is equivalent).

Exam ple

%%[Delete: YES]


Using embedded addressing with mail merge

Mail merge is used most frequently for merging mailing address details to a standard letter in order to send personalized copies to a list of recipients. The resulting documents are then printed to a network paper printer on company letterhead and mailed to the recipient. The embedded addressing feature of the Zetafax API can be used to send faxes to multiple recipients from a list generated by a contact manager or database.

Using Zetafax

In the same way, the addressing data fields can be replaced with fax addressing information by inserting mail merge fields in your word processing template enclosed within the Zetafax embedded addressing syntax. The addressing information is inserted when the mail merge is performed and instead of printing to a network paper printer, simply printing to the Zetafax printer renders the fax to the queue at the Zetafax server. At this stage, you can also tell Zetafax to overlay the document to your company's letterhead. For example, a section in a Microsoft Word template may look something like:

254	Zetafax 2012 A	PI Help		
FAXSHOT.doc - Microsoft Word				
<u>File Edit View Insert Format Tools Table Window H</u> elp Acrobat				
🗋 🗁 🖬 🚑 🥝 🚑 🖪 🥸 🐇 🖻 🛍 ダ 🗠 - ལ - 🍓 🗗 🗔 🖼 👭 👖 90% 🔹 🤻				
Normal • MetaPlus • 10 • B I U 📰 🚍 🚍 🗄 🗄 🕼 🖉 • 🗛 • 🔜 🐥				
Insert Merge Field - Insert Word Field - Set IN - I III → N 🖷 🕸 Serge 🙀 🖬 -				
L 3	. 1 · 2 · 1 · 1 · 1 · [·	₩ 1 1 1 · 2 · 1 · 3 · 1 · 4 · 1 · 5 · 1 · 6 · 1 · 7 · 1 · 8 · 1 · 9 · 1 · 10 · 1 · 11 · 1 · 12 · 1 · 13 ·		
-	%%[TO: «F	axNumber»,«FullName»,«Organization»]		
	FAX MES	FAX MESSAGE		
	Date:	%%[DATE]		
~	To:	%%[NAME]		
	Company:	%%[ORGANISATION]		
	From:	%%[FROM]		
4	Pages:	%%[PAGES] (including this one)		
5 -	If you do not	If you do not receive all of this message please contact the sender on (770) 123 4000		
۰ م	Dear «Salut:	Dear «Salutation»,		
. 2.				
Page 1	Sec 1 1/	1 At 2.5cm Ln 1 Col 1 REC TRK EXT OVR English (U.K		

Related topics Embedding addressing information Options commands Action commands



The ZSUBMIT program

The ZSUBMIT program is a part of the API toolkit which lets DOS, mini and mainframe programs send faxes and text messages by creating text files in a shared directory on a file server. For example, faxing purchase orders or invoices usually only requires adjusting an accounts packages report writer. A text file needs a few lines added to give the fax/mobile number and message options. Logos and signatures can be included and the text may be merged onto a multi-page form using the letterhead feature in Zetafax. This approach gives results rapidly.

This section introduces and explains in depth the format of submit files required by the ZSUBMIT program. Typically, this section can be used as a reference for both users of ZSUBMIT and the COM and C language APIs. Finally, there are some example SUBMIT files giving instances of its use.

<u>Creating SUBMIT files</u> <u>SUBMIT file Message Option lines</u> <u>SUBMIT file Message Addressing lines</u> <u>SUBMIT file Message Text commands</u> <u>Action commands</u> <u>Example SUBMIT files</u> <u>Sending SMS messages</u> <u>Example SMS SUBMIT files Submitting SUBMIT files Sending ASCII text files as messages</u>

Creating SUBMIT files

One of the API methods of submitting messages for sending is to create a file in a specific format, termed SUBMIT file format. This is an ASCII text file that usually contains details of the options to use in preparing the message, the recipients of the message, as well as the message text itself. ZSUBMIT files have the .sub file extension.

ZSUBMIT program

The message may then be sent using the ZSUBMIT program. This program may be installed to run continuously as one of the Zetafax server programs, regularly checking a particular directory for the existence of a SUBMIT format file. If one is found then it is interpreted and submitted to the Zetafax server for sending - its progress may then be monitored using the client program as normal.

The ZSUBMIT program submits all messages as a given Zetafax user, and if required will monitor progress of the messages, limiting the number of outstanding messages at any one time or removing any entries which have been sent without errors. Files for sending via the ZSUBMIT program may also contain more than one message for sending - the program will split it into separate messages before submitting it to the server.

Use with API calls

SUBMIT format files are also used by the Application Programmers Interface (API) routines to specify message options and text for sending. These routines allow user written application programs to send messages directly without using either the client or ZSUBMIT program. The ZSUBMIT program itself is written using these routines, and requires the API toolkit license to run.

SUBMIT file format

This section details the format of SUBMIT files, for use with both the ZSUBMIT program and with the API routines. It gives the structure and fields allowed in the file for specifying message options and recipients, and also for formatting the message text.

The SUBMIT file is a standard ASCII text file (multiple lines, each terminated with CR LF). The file contains information about the options to be used in preparing a given message, the recipients, and the message text itself. The format is:

%%[MESSAGE]
Message option lines
Message addressing lines

%%[TEXT] Text including message text fields

To specify a separate file containing the message to be sent (e.g. to send a graphics file):

%%[MESSAGE]
Message option lines
Message addressing lines

%%[FILE]
Filename, including path

Note: The first line of the file must be "%%[MESSAGE]".

The section headings ("%%[MESSAGE]" and "%%[TEXT]" or "%%[FILE]"), all message option and

addressing lines, and the filename (if the second form is used) must start at the left of the line (i.e. there must be no spaces preceding them). Finally, tab characters should not be used in the file - they will be replaced with a space character.

Multiple messages

Files submitted using the ZSUBMIT program may contain information about one or more messages by simply concatenating the files (i.e. the %%[MESSAGE] section for the second message follows the end of the %%[TEXT] or %%[FILE] sections for the first message, etc.). The ZSUBMIT program splits the file into separate messages before submitting them to the server.

Multiple message files

The Zetafax server also supports the sending of multiple message files specified within a SUBMIT file. When a message file is specified in the %%[FILE] section, typically ~SEND000.G3F, .EPN or .TXT in the OUT directory, the Zetafax server will scan for matching files with extension .001, .002 and append these files to the fax message. Additionally, SUBMIT files can also contain more than one %%[TEXT] or %%[FILE] sections, and both ZSUBMIT and the API library functions will generate a series of message files using the new .001 naming convention.

Use with COM and C libraries

SUBMIT files used with the API functions may only contain information for a single message - everything from the first %%[TEXT] command to the end of the file is treated as message text. Certain of the functions only look at one of the two sections - in this case the other section may of course be omitted.



SUBMIT file Message Option lines

These lines appear at the start of the %%[MESSAGE] section, before the addressing lines (i.e. before the first "To:" line). If omitted, all the lines (except the "Comment:", "Attach" and "Charge" lines) default to the values specified for the given user. For files submitted by programs using the API functions, this is the user specified in the ZfxAPIInit call. For files submitted using the ZSUBMIT program, it is the user specified in the W%[MESSAGE] section (if given), or in the SETUP.INI file.



After

Syntax

AFTER: time

where time specifies the earliest time that the message should be sent, for deferred sending. The format of the time field may be one of the following:

yy-mm-dd hh:mm:ss (date and time specified) OFFPEAK(as defined in SETUP.INI)

If the time field is omitted the message is queued for sending immediately.

Description

Specifies when the message is to be sent.

Example

After: 02-07-31 18:00:00



Attach

Syntax

ATTACH: files

where files is a comma separated list of graphics files to attach to the fax.

Description

Specifies the attachment files in the user's private graphics directory (Z-GRAPH) or in the system graphics directory. These are added to the end of the fax before sending. A maximum of 30 files may be specified.

Example

Attach: INFOPACK, PRICES



Charge

Syntax

CHARGE: chargecode

where chargecode specifies the charge code to use for this message, and may be any text.

Description

Specifies the charge code to use for this message. Charge codes are stored in the Zetafax billing log when the message completes, and may be used for charging the message to a particular department or client.

Example

Charge: Sales Dept



Comment

Syntax

COMMENT: comment

where comment is the message description (up to 40 characters long).

Description

Specifies the message description as displayed on the right of the client OUT window. If this line is omitted a message description detailing the first addressee is used.

Example

Comment: Smith and Co January invoice



Coversheet

Syntax

COVERSHEET: coversheet

where coversheet is the name of the file to be used to generate a coversheet for the fax (1 to 8 characters long) or blank for no coversheet.

Description

Specifies what coversheet to generate for the fax onto before sending.

Example

Coversheet: COVSHEET



Covertext

Syntax

COVERTEXT: covertext

where covertext is the next line of covernote text to be added to the coversheet.

Purpose

specifies the text to be added to the coversheet selected in the "COVERSHEET:" message option line. This line can be repeated as many times as required, though all of the COVERTEXT: lines must be together and as they are message options they must occur before the first "To:" line. Zetafax only uses the number of COVERTEXT: lines defined in the coversheet - if the coversheet contains ten "%%[NOTE]" fields, and the submit file has twelve COVERTEXT: lines, the last two COVERTEXT: lines will be ignored.

Example

COVERTEXT: Here is the price list as promised. COVERTEXT: Please call if you have any queries. COVERTEXT: Regards, COVERTEXT: Sam Smith



Delete

Syntax

DELETE: delete

where delete is either "YES" or "OK".

Purpose

Specifies whether the server should delete a message from the OUT directory after it has completed. If set to "OK" the message will only be deleted if sent successfully, while setting it to "YES" causes it to be deleted on completion whether successful or not.

Example

Delete: YES



Format

Syntax

FORMAT: format

where format specifies the file format of the data file to be sent. The possible values of the format field (together with the data type and the associated data file extensions) are:

ASCII(ASCII text, unformatted - TXT) EPSON(Epson FX or LQ print spool file - EPN) TIFF-NORMAL(200x100 dpi TIFF fax file - G3N) TIFF-FINE(200x200 dpi TIFF fax file - G3F)

Description

Specifies what format the data file is in. In a standard SUBMIT file (containing a %%[TEXT] section) the format should be "EPSON" or "ASCII". Epson should be used if the message text contains any "%%" formatting commands (e.g. "%%[BOLD:ON]"). If however the message text just contains ASCII text then the format should be specified as "ASCII" (or the line omitted), in which case the result will be the same as using the client to send an ASCII text file.

Example

FORMAT: EPSON



From

Syntax

FROM: sendername

where sendername is the originator of the message.

Description

Specifies the name that is put on the fax cover sheet as the sender of the fax (cf the From: field on the Zetafax addressing dialog).

Example

From: Sam Smith



Header

Syntax

HEADER: header

where header is one or more of No, To, Fr, Da and Ti (with no separating spaces), as follows:

No	Page numbering (n/N)
То	Name of recipient
Fr	Name of sender
Dt	Date
Ti	Time
Fr Dt	Name of sender Date

Description

Specifies the format of the header line to appear at the top of each page of the fax.

Example

Header: NoToFrDa



Hold

Syntax

HOLD: hold

where hold is either "YES" or "NO".

Description

Specifies whether the message will be held once it in the queue, meaning that it will not be sent until the user releases it, using the Zetafax client Release command (File Menu). This gives a similar effect to the Hold for preview before sending check box on the Zetafax client addressing dialog, allowing the fax to be checked on screen before sending.

Example

Hold: YES



Letterhead

Syntax

LETTERHEAD: letterhead

where letterhead is the name of the file to be used as the letterhead (1 to 8 characters long) or blank for no letterhead

Description

Specifies what letterhead to merge the fax onto before sending.

Example

Letterhead: LETTHEAD



Preview

Syntax

PREVIEW: preview

where preview is either "YES" or "NO".

Description

Specifies whether a preview file is to be prepared for this message. This is a copy of the fax prepared for the first recipient, which can be viewed using the View (File menu) option on the Zetafax client. The default setting is "YES", but if disk space is limited and there is no requirement to view the faxes from a client then this parameter may be set to "NO".

Note: To preview the fax on the Zetafax client before it is sent (in a similar way to the Hold for preview before sending check box on the Zetafax client addressing dialog) you should set this option to "YES" (the default), and also set the Hold: message option (qv).

Example

Preview: NO



Priority

Syntax

PRIORITY: priority

where priority is one of "URGENT", "NORMAL" or "BACKGROUND".

Description

Specifies the priority to be used when queuing the message, in the same way as the Priority radio button on the client sending options dialog.

Example

Priority: NORMAL



Quality

Syntax

QUALITY: quality

where quality is one of "DRAFT", "NORMAL" or "HIGH".

Description

Specifies the resolution to be used when sending the fax, in the same way as the Resolution button on the client sending options dialog. For fax, "DRAFT" and "HIGH" will normally force the fax to be sent at standard (200x100 dpi) and fine (200x200 dpi) resolutions respectively, whilst "NORMAL" will send at whichever resolution has been specified by the system administrator in the system initialization file.

Example

Quality: NORMAL



Subject

Syntax

SUBJECT: subject

where subject is the message subject (up to 60 characters long).

Description

Specifies the message subject, as displayed on the right of the client OUT window. If a coversheet is being sent, the subject line will be included on the coversheet.

Example

Subject: Smith and Co January invoice



User name

Syntax

USER: username

where username specifies a valid Zetafax user name.

Description

Specifies the Zetafax user submitting this file. The command may be omitted if the default user name specified in the [ZSUBMIT] section in the SETUP.INI initialization file was not blank, or if submitting using the API COM or C language functions.

Note - this command can only be used in files submitted using the ZSUBMIT program (rather than using the API "C" function calls, where the name is specified in the ZfxAPIInit function). The ZSUBMIT program can be configured to disable this command, if desired for permissions or security reasons.

Example

User: JSMITH



SUBMIT file Message Addressing lines

These lines appear in the <code>%%[MESSAGE]</code> section, after the message options lines detailed in the <u>SUBMIT file</u> <u>Message Option lines</u> topic.

Note: A"To:" line must be first line specified (after the last message option line), before any other message addressing lines. The lines may be repeated if the message is to be sent to more than one person, with each repeated set starting with a "To:" line.

Fax SMS Field User name Organisation To



Fax

Syntax

FAX: number

where number is the fax telephone number (cf the Zetafax address book editor fax number field).

Description

Specifies the fax number to send the fax to. If the number is unknown at the time of creating the file the number can be omitted. The Zetafax server will reject the send to that recipient, and the message can be resubmitted manually entering the fax number as required.

Default

None - mandatory field (unless LAN: or SMS: line is specified - see below).

Example

Fax: 456 789 0123



SMS

Syntax

SMS: number

where number is the mobile telephone number of the recipient.

Description

Specifies the mobile telephone number to send the message to. SMS messages are submitted via an SMS center on the mobile network. The telephone number for the message center is configured in the Devices section of the Zetafax Configuration program and it is not necessary to specify it in the SUBMIT file.

Default

None - mandatory field (unless LAN: or FAX: line is specified - see below).

Example

SMS: 456 789 0123



Field

Syntax

FIELD: fieldname text

where fieldname is a single word (i.e. without any spaces) giving the name of a Embedded Command field, and text is the string which will be substituted for the field.

Description

Embedded Command fields are identified in a document by the string "%%[fieldname]" (without the double quotes). When the fax is prepared for sending these fields are replaced with the text given, allowing faxes to multiple addressees to be personalized, for example. Multiple FIELD lines may be specified.

Note: The Field lines are not retained if a message is resubmitted using the Zetafax client program (for example, to correct a fax number).

The following field names are reserved, and should not be used with this command:

- COVERTEXT
- ORGANISATION
- DATE
- PAGE
- FONT
- PAGES
 FROM
- FROMPORTRAIT
- LANDSCAPE
- SUBJECT
- NAME
- TIME
- NOTES

Default

None - any fields not specified are treated as blank.

Example

Field: Department Sales and Marketing



User name

Syntax

LAN: username

where username is the Zetafax username of the person to be sent to.

Description

Specifies the name of the Zetafax user for messages which are to be sent across the LAN (appearing in the user's IN window). This can be useful when testing applications to check the appearance of faxes to be sent without actually sending them to the remote user, in the same way as one might use Preview from the client.

Default

None - used as an alternative to the Fax: line.

Example

LAN: Fsmith



Organisation

Syntax

ORGANISATION: organisation

where organisation is the name of the company or organisation to which the fax recipient belongs.

Description

The organisation name is used on the coversheet of fax messages.

Default

Blank.

Example

Organisation: Smith and Sons Limited



То

Syntax

TO: name

where name is the name of the person to whom the message is to be sent.

Description

Specifies a recipient of the fax (cf the Coversheet Name field in the Zetafax address book). This name is used on the coversheet of the fax, on the header line of the fax, and also in the comment on the right hand side of the OUT window in the client display, Unless overridden by the comment message options line.

Default

None - mandatory line.

Example

To: Sam Smith



SUBMIT file Message Text commands

These commands appear in the %%[TEXT] section and may be freely interspersed with the message text.

See the Embedded Command description in <u>SUBMIT file Message Addressing lines</u> for details about what to do if you need to include the characters "%%[" in the message, without them being treated as a command.

Append Bold Date Down Field name Font Insert Landscape Left margin Page Portrait Right Time Underline



Append

Syntax

%%[APPEND:file]

where *file* is the base name of a graphics file in the Z-GRAPH directory.

Description

Appends a graphics image (e.g. a scanned information sheet) to the end of the message (similar to the Zetafax client **Attach** option). Up to 30 of these commands may be entered, and the named files will be added to the end of the message as new pages. This command can also be used in separate ASCII format files specified using the %%[FILE] option.

Example

%%[Append:INFOPAGE]



Bold

Syntax

%%[BOLD:state]

where state is either "ON" or "OFF".

Description

The %%[BOLD:ON] command causes all characters following to be printed in bold within the fax message until either a %%[BOLD:OFF] command is encountered or the end of the %%[TEXT] section is reached.

Example

%%[Bold:ON]



Date

Syntax

%%[DATE]

Description

Inserts the date when the message is prepared for sending, in the format "31st August 2005". This command can also be used in separate ASCII format files specified using the %%[FILE] option.

Example

%%[Date]



Down

Syntax

%%[DOWN:distance]

where distance is the number of units to move down the page from the current position. A unit is approximately 1/100th of an inch.

Description

This command moves down the page a given distance and may be used, for example, to position the top line of text to fit within a merged form.

Note: The first line of text prints approximately 0.7 inches below the top of the page.

Example

%%[Down:100]



Field name

Syntax

%%[fieldname]

where fieldname is the name of an Embedded Command.

Description

Inserts the text for the given field for that addressee. The following fieldnames are defined for all messages submitted using the API or ZSUBMIT program:

- FROM
- NAME
- ORGANISATION

Other fields are only defined if they have been specified using the Field: message addressing line (see SUBMIT file Message Addressing lines). This command can also be used in separate ASCII format files specified using the %%[FILE] option.

Example

%%[Organisation]


Font

Syntax

%%[FONT:font{,size}{,B}{,I}]

where *font* is the font required, and is any TrueType font available on the Zetafax server. Alternatively, for compatibility with previous versions, one of "ROMAN10", "ROMAN12", "ROMAN20", "ROMAN5", "ROMAN6" or "ROMANPS" gives 10cpi, 12cpi, 20cpi, 5cpi and 6cpi fixed space fonts, and proportional spaced font respectively.

Description

This command is used to set the font to be used for the remainder of that message (i.e. until the end of the %[TEXT] section).

Example

%%[Font:Arial,10]



Insert

Syntax

%%[INSERT:file]

where *file* is the base name of a graphics file in the Z-GRAPH directory.

Description

Inserts a single page graphics image (e.g. a signature) at the current position on the page. The image is merged into the faxed document - you must leave enough lines following the command blank if you wish to avoid the image overprinting the following text. This command can also be used in separate ASCII format files specified using the %%[FILE] option.

Example

%%[Insert:ABCLOGO]



Landscape

Syntax

%%[LANDSCAPE]

Description

This command causes the text which follows (until a %%[PORTRAIT] command or the end of this message, whichever comes first) to be printed in landscape orientation. The command must come before any other text - i.e. at the start of the first line following the %%[MESSAGE] command, or immediately after a %% [PAGE] command (on the same line). This command can also be used in separate ASCII format files specified using the %%[FILE] option.

Example

%%[Landscape]



Left margin

Syntax

%%[LMARGIN:width]

where *width* is the size of the left hand margin in character widths. The width of each character is dependent upon the font being used.

Description

This command is used to set the left margin for the remainder of that message (i.e. until the end of the % [TEXT] section). It should be placed at the start of a line.

Note: The margin width excludes a strip of width 0.5 inches at the left of the page which may not be used (i.e. a value of 0 would set the left hand margin 0.5 inches from the left of the page).

Example

%%[LMargin:200]



Page

Syntax

%%[PAGE]

Description

This command is used to start a new page.

Example

%%[Page]



Portrait

Syntax

%%[PORTRAIT]

Description

This command cancels a previous %%[LANDSCAPE] command, reverting to portrait orientation. The command must come before any other text - i.e. at the start of the first line following the %%[MESSAGE] command, or immediately after a %%[PAGE] command (on the same line).

Note: The margin settings following a %%[PORTRAIT] command are different from the defaults for ASCII files, allowing slightly more of the page to be printed. This can be useful when overprinting forms, for example. This command can also be used in separate ASCII format files specified using the %%[FILE] option.

Example

%%[Portrait]



Right

Syntax

%%[RIGHT:distance]

where distance is the number of units to the right from the current position. A unit is approximately 1/100th of an inch.

Description

This command moves across the page to the right a given distance and may be used, for example, to position a word precisely within a form.

Example

%%[Right:100]



Time

Syntax

%%[TIME]

Description

Inserts the time when the message is prepared for sending, using a 24 hour clock, in the format "12:34". This command can also be used in separate ASCII format files specified using the %%[FILE] option.

Example

%%[Time]



Underline

Syntax

%%[UNDERLINE:state]

where state is either "ON" or "OFF".

Description

The %[UNDERLINE:ON] command causes all characters following to be printed underlined until either a %[UNDERLINE:OFF] command is encountered or the end of the %%[TEXT] section is reached.

Example

%%[Underline:ON]



Action commands

These remaining commands may be used within a document to split it into a number of faxes.

<u>Send</u> Preview



Send

Syntax

%%[Send]

Description

Indicates that the document being printed should be split at the foot of this page and submitted as a fax. The remaining page or pages will be treated as a separate fax or faxes.

Example

%%[Send]



Preview

Syntax

%%[Preview]

Description

Indicates that the document being printed should be split at the foot of this page and submitted as a fax for preview. The remaining page or pages will be treated as a separate fax or faxes.

Example

%%[Preview]

Example fax SUBMIT files

Simple message

%%[MESSAGE] User: JJONES From: Jim Jones To: Sam Smith Organisation: Smith and Sons Fax: 456 789 0123

%%[TEXT] Dear Sam Here's a short fax produced automatically Yours, Jim

Multiple messages

%%[MESSAGE] User: JJONES From: Jim Jones To: Sam Smith Organisation: Smith and Sons Fax: 456 789 0123 %%[TEXT] Hello Sam!

%%[MESSAGE] User: JJONES From: Jim Jones Coversheet: COVSHEET To: Alan Ayton Fax: 456 789 0123 %%[TEXT] Hello Alan!

Multiple addressees

%%[MESSAGE] User: SSMITH From: Sam Smith Coversheet: COVSHEET Letterhead: LETTHEAD To: Sam Smith Organisation: Smith and Sons Fax: 456 789 0123

To: Jim Jones Organisation: Jones Brothers Fax: 123 456 7890 %%[TEXT] Don't forget the steering group meeting this evening Sam

Multiple message files

%%[MESSAGE] User: JJONES From: Jim Jones To: Sam Smith

Zetafax 2012 API Help

Organisation: Smith and Sons Fax: 456 789 0123 %%[TEXT] Here are the brochure and price list I promised to send.I've included the general brochure as I thought this would be more helpful. %%[FILE] C:\Program Files\Zetafax Server\SERVER\Z-TEMP\BROCHURE.G3F %%[FILE] C:\Program Files\Zetafax Server\SERVER\Z-TEMP\PRICES.G3F %%[TEXT] Please call me if you have any other questions Text formatting %%[MESSAGE]

User: JJONES From: Jim Jones Coversheet: COVSHEET Letterhead: LETTHEAD Syntax EPSON To: Sam Smith Organisation: Smith and Sons Fax: 456 789 0123

%%[TEXT] %%[LMARGIN:200] %%[DOWN:200] %%[FONT:ROMAN10]

302

Dear Jim Here's a%%[BOLD:ON]short fax%%[BOLD:OFF] produced automatically %%[PAGE]%% [DOWN:200]This is the second page Now to end the letter with a signature added using the standard "insert graphics" command. Yours%%[INSERT:JIMSIG] Jim Jones



Sending SMS messages

The Zetafax server is capable of submitting Short Message Service (SMS) or text messages to mobile devices using the commands specified below. SMS messages are submitted via an SMS center before being delivered to the mobile device.

SMS messages are limited to 160 characters per short message. Longer messages can be sent using Zetafax, the Zetafax server handles longer SMS messages by breaking one long message into several smaller messages. Preferences for handling longer messages can be modified in the **Zetafax Configuration** program under the **Devices** note for each SMS device you have configured.

Message commands

SMS messages can handle message text only, and cannot be used to send graphics files or other file formats. As a result, several Message Option and Message Text commands that can be used to create fax messages are not relevant when sending SMS messages. It is also important to include "Coversheet: ". This denotes that you do not wish to use a coversheet which are not supported by SMS messages.

The following is a list of Message Option commands that are supported when sending SMS messages. For a detailed description of each command, refer to <u>SUBMIT file Message Option lines</u>.

Command	Description	
After	Specifies the earliest time that the message should be sent.	
Charge	Specifies a charge code to use for a message.	
Comment	Specifies the message description.	
Delete	Specifies whether the Zetafax server should delete the message from the OUT	
	directory after it has completed.	
Format	Specifies what format the data file is in.	
Hold	Specifies whether the message will be held once it in the queue, meaning that it will not be sent until the user releases it .	
Priority	Specifies the priority to be used when queuing the message.	
Subject	Specifies the message subject, as displayed in the client OUT window.	
User	Specifies the Zetafax user submitting this file.	

The following Message Option commands are not applicable and are therefore not supported when sending SMS messages using ZSUBMIT:

- ATTACH,
- COVERSHEET,
- COVERTEXT,
- FAX,
- FIELD,
- FROM,
- HEADER,
- LAN,
- LETTERHEAD,
- ORGANISATION,
- PREVIEW,
- QUALITY.

The following Message Text commands are not supported when submitting SMS messages using ZSUBMIT:

- %%[APPEND],
- %%[BOLD],
- %%[DOWN],
- %%[FONT],
- %%[INSERT],

- %%[LANDSCAPE],
 %%[LMARGIN],
 %%[PAGE],
 %%[PORTRAIT],
 %%[RIGHT],
 %%[UNDERLINE].

Example SMS SUBMIT files

Simple message

%%[MESSAGE] User: JJONES Coversheet: To: Sam Smith SMS: 456 789 0123

%%[TEXT] Dear Sam Here's a short SMS message produced automatically Yours, Jim

Multiple messages

%%[MESSAGE] User: JJONES Coversheet: To: Sam Smith SMS: 456 789 0123

%%[TEXT] Hello Sam!

%%[MESSAGE] User: JJONES Coversheet: To: Alan Ayton SMS: 123 456 7890

%%[TEXT] Hello Alan!

Multiple addressees

%%[MESSAGE] User: JJONES Coversheet: To: Sam Smith SMS: 456 789 0123 Coversheet: To: Alan Ayton SMS: 123 456 7890

%%[TEXT] Don't forget the steering group meeting this evening Sam

Multiple message files

%%[MESSAGE] User: JJONES Coversheet: To: Sam Smith SMS: 456 789 0123

Zetafax 2012 API Help

%%[TEXT] Here's the price list I promised to send to you.

306

%%[FILE] C:\Program Files\Zetafax Server\SERVER\Z-TEMP\PRICES.TXT %%[FILE] C:\Program Files\Zetafax Server\SERVER\Z-TEMP\BUSCARD.TXT

%%[TEXT] Please call me if you have any questions.



Submitting SUBMIT files

When using the ZSUBMIT program, files in SUBMIT file format may be submitted by simply copying them to a file in the specified directory with the extension ".SUB". If the file contains more than one "%% [MESSAGE]" section (i.e. contains more than one message to be sent) then it is first split up by the program into separate message files in the polling directory, named ~ZSUBnnn.SUB, where "nnn" is a unique number for each file. Each file is then interpreted separately and submitted to the server for sending.

Syntax errors

If an error is found in the format of one of the files (e.g. an invalid or missing line in the message options), an error message is logged giving the problem and file name, and the file extension is changed to ".ERR"; otherwise the file is deleted once it has been separated (in the case of multiple message files) or submitted successfully. This directory should be checked if submit errors occur to identify the problem then delete the ".ERR" file - performance of the program will be affected if the number of files in the directory is allowed to become very large.

Automatic deletion

ZSUBMIT deletes SUBMIT files automatically once they have been processed and submitted to the Zetafax server. It will also delete matching files with extensions .001, .002 etc., continuing until it does not find the next file in sequence. This makes it simple to submit messages comprising multiple files, without having to tidy up manually.

Conversely, if a file is used by more than one SUBMIT file, it should not be given an extension of .001.

File creation

It is important to ensure that the submit file is complete (and any files it references exist), from the moment when the ZSUBMIT program might try and read it.

The ZSUBMIT program will behave correctly if the .SUB file is locked, retrying until it can access the file; however this can still give inaccurate results with some applications. With some programs, the file can be accessed and is "readable" even while it is being created, whilst others can create a zero length file first before reopening it to write the data. The symptom is occasional failures when ZSUBMIT tries to read the file at the precise moment it is being created.

The best and recommended approach is to create the file with a different extension e.g. .NEW and rename it to .SUB only when it is complete.



Server settings options for sending ASCII text files as messages

You can set up Zetafax to send ASCII text files as messages in the **Server settings** options of the Zetafax Configuration program. These options are used if a text file is sent directly using the Zetafax Client **File Send** option, rather than printed from a word processor (using the Zetafax printer driver).

• To display this dialog, double-click **Sending ASCII text files** in **Server settings**, or select the **Text files** icon from the **Zetafax - configuration options** dialog.

Top margin

Range 0 - 15 lines.

Specifies the number of blank text lines at the top of the fax page when preparing an ASCII text file for sending.

Bottom margin

Range 0 - 15 lines.

Specifies the number of blank text lines at the bottom of the fax page when preparing an ASCII text file for sending.

Page length

Range 35 - 100 lines.

Specifies the number of text lines per page (including the top and bottom margins) when preparing an ASCII text file for sending. A value of 72 gives approximately an A4 page.

OK

Save any changes that have been made to the ASCII text files configuration, and exit the Zetafax - configuration options dialog.

Cancel

Do not save changes made to the ASCII text files configuration, and exit the Zetafax - configuration options dialog.

Reset

Reset the ASCII text files configuration to its default settings. The settings are not saved until either **OK** is clicked or another category icon is selected from the scroll (left). If you use the scrolling icons on the left to move to another **Category**, any changes made to the ASCII text files configuration are saved.

Index

- A -

API configuration 14

- C -

C Language API 135 Converting from older versions 138 Function error returns and reference 155 140 Function overview 148 Message defaults Message information 142 Message transmission history 145 Server and device status 150 CAPI alphabetical reference 158 user error 160 ZfxAbortMsg 161 ZfxAPIClosedown 162 ZfxAPIInit 163 ZfxCheckNewMsgStatus 165 ZfxCheckServer 167 ZfxCreateAutoFile 168 ZfxCreateCtlFile 170 ZfxCreateCtlFileEx 172 ZfxCreateCtIFileFP 174 ZfxCreateDataFile 176 ZfxCreateDataFileFP 177 ZfxDeleteMsg 179 ZfxGetAPIVersion 181 ZfxGetMsgDefaultsEx 183 ZfxGetMsgHistory 184 ZfxGetMsgHistoryEx 187 ZfxGetMsgInfo 190 ZfxGetMsgInfoEx 192 194 ZfxGetMsgList ZfxGetMsgListEx 196 198 ZfxGetServerStatus ZfxGetServerStatusEx 200 ZfxGetSystemArea 202 ZfxGetUserArea 203 ZfxGetUserCoversheet 204 ZfxGetUserFromname 206 ZfxGetUserInDir 208

ZfxHoldMsg 209 ZfxMarkMsgAsRead 210 ZfxReleaseMsg 211 ZfxRestartServer 212 ZfxRushMsg 213 ZfxSendMsg 215 ZfxSendMsgEx 217 ZfxSendSubmitFile 219 ZfxSendSubmitFileFP 221 ZfxStartServer 223 ZfxStopServer 224 225 ZfxVBSendSubmitFile COM API 23, 34, 118 Change History 133 Errors 32 Overview 24 ZfLib APIPrint 36 ZfLib APIPrint.CancelPrint 37 ZfLib APIPrint.FileName 37 ZfLib APIPrint.lsComplete 37 ZfLib APIPrint.StartPrint 38 ZfLib Attachment 38 ZfLib Attachment.Delete 39 39 ZfLib Attachment.Name ZfLib Attachments 39 ZfLib Attachments.Add 40 ZfLib Attachments.Count 41 ZfLib Attachments.Item 41 ZfLib Coversheet 41 ZfLib Coversheet.Name 42 ZfLib Coversheets 42 ZfLib Coversheets.Count 42 ZfLib Coversheets.Item 43 ZfLib Device 43 ZfLib Device.CurrentPage 44 ZfLib Device.MessageBody 44 ZfLib Device.Name 45 ZfLib Device.User 47 ZfLib Devices 47 ZfLib Devices.Count 47 ZfLib Devices.Item 48 ZfLib DevStatusEnum 121 122 ZfLib EventEnum ZfLib FaxTypeEnum 123 48 ZfLib File ZfLib File.Delete 49 ZfLib File.FileName 49 ZfLib Files 49

COM API 23, 34, 118 ZfLib Files.Count 50 ZfLib Files.Item 51 ZfLib FormatEnum 123 ZfLib HeaderEnum 124 ZfLib Inbox 51 ZfLib Inbox.CheckNewMsgStatus 52 ZfLib Inbox.GetMsg 52 ZfLib Inbox.GetMsgList 52 ZfLib Letterhead 53 ZfLib Letterhead.Name 53 ZfLib Letterheads 53 ZfLib Letterheads.count 54 ZfLib Letterheads.Item 54 ZfLib Link 55 ZfLib Link.ConnectionOK 56 ZfLib Link.LinkActive 56 ZfLib Link.LocalStatus 56 ZfLib Link.NumAcknowledged 57 ZfLib Link.NumDeviceError 57 ZfLib Link.NumRemoteServerError 58 ZfLib Link.NumSenkOK 59 ZfLib Link.NumUnAcknowledged 59 ZfLib Link.RemoteServer 60 ZfLib Link.RemoteStatus 60 ZfLib Links 60 ZfLib Links.Count 61 ZfLib Links.Item 61 ZfLib LinkStatusEnum 125 ZfLib Message 62 ZfLib Message.AbortMsg 63 ZfLib Message.DeleteMsg 63 ZfLib Message.GetMsgHistories 63 ZfLib Message.GetMsgInfo 64 ZfLib Message.HoldMsg 64 ZfLib Message.MarkMsgAsRead 64 ZfLib Message.ReleaseMsg 64 65 ZfLib Message RushMsg ZfLib Message.SendMsg 65 ZfLib MessageHistories 65 ZfLib MessageHistories.Count 66 ZfLib MessageHistories.Item 66 ZfLib MessageHistory 67 ZfLib MessageHistory.AddrNum 67 ZfLib MessageHistory.Connection 68 ZfLib MessageHistory.Date 68 ZfLib MessageHistory.Device 69 ZfLib MessageHistory.ErrorCode 69

ZfLib MessageHistory Event 69 ZfLib MessageHistory.Name 70 ZfLib MessageHistory.Organisation 70 ZfLib MessageHistory.PagesSent 71 ZfLib MessageHistory.RemoteServer 71 ZfLib MessageHistory.Route 71 ZfLib MessageHistory.RouteParams 72 ZfLib MessageInfo 72 73 ZfLib MessageInfo.Body ZfLib MessageInfo.Comment 74 ZfLib MessageInfo.CustomField 74 ZfLib MessageInfo.ImageFilePath 75 ZfLib MessageInfo.ImageSize 75 ZfLib MessageInfo.ImageStream 75 ZfLib MessageInfo.Organisation 75 ZfLib MessageInfo.Status 76 ZfLib MessageInfo.Subject 76 ZfLib MessageInfo.Type 76 ZfLib MessageInfo.UserStatus 77 ZfLib Messages 77 78 ZfLib Messages.Count 78 ZfLib Messages.Item ZfLib Messages.MsgDir 79 ZfLib NewMessage 79 ZfLib NewMessage,After 81 ZfLib NewMessage.Attachments 81 ZfLib NewMessage.Body 82 ZfLib NewMessage.Charge 82 ZfLib NewMessage.Comment 83 ZfLib NewMessage.CoverSheet 83 ZfLib NewMessage.Covertext 84 ZfLib NewMessage.CustomField 84 ZfLib NewMessage.Delete 84 ZfLib NewMessage.Files 85 ZfLib NewMessage.Format 85 ZfLib NewMessage.From 86 86 ZfLib NewMessage.Header ZfLib NewMessage.Hold 87 87 ZfLib NewMessage.Letterhead ZfLib NewMessage.Preview 88 ZfLib NewMessage.Priority 88 ZfLib NewMessage.Quality 89 ZfLib NewMessage.Recipients 89 ZfLib NewMessage.Send 90 90 ZfLib NewMessage.SendTime 90 ZfLib NewMessage.Subject ZfLib NewMessage.Text 91 ZfLib NewMessage.User 91

	Index 311
COM API 23, 34, 118	ZfLib UserSession.Inbox 109
ZfLib Outbox 92	ZfLib UserSession.Logoff 110
ZfLib Outbox.CheckNewMsgStatus 92	ZfLib UserSession.Outbox 110
ZfLib Outbox.GetMsg 93	ZfLib UserSession.SendSubmitFile 110
ZfLib Outbox.GetMsgList 93	ZfLib UserSession.Server 111
ZfLib PriorityEnum 125	ZfLib UserSession.SystemArea 111
ZfLib QualityEnum 126	ZfLib UserSession.UserInDir 112
ZfLib Recipient 93	ZfLib UserSession.UserOutDir 112
ZfLib Recipient. Delete 94	ZfLib UserSessionUserArea 111
ZfLib Recipient.Fax 94	ZfLib UserStatusEnum 129
-	ZfLib ZfAPI 112
	ZfLib ZfAPI.GetZetafaxServerInfoFromAD 113
ZfLib Recipient.To 95	ZfLib ZfAPI.GetZetafaxServersFromAD 114
ZfLib Recipient.Type 96	
ZfLib Recipients 96	ZfLib ZfAPI.LognAnonymous 115
ZfLib Recipients.AddFaxRecipient 97	ZfLib ZfAPI.Logon 114
ZfLib Recipients.AddLANRecipient 98	ZfLib ZfAPI. RequestDir 115
ZfLib Recipients.AddSMSRecipient 98	ZfLib ZfAPI.ServerDir 116
ZfLib Recipients.Count 99	ZfLib ZfAPI.SetZetafaxDirs 116
ZfLib Recipients.Item 99	ZfLib ZfAPI.SetZetafaxServerFromAD 116
ZfLib RouteEnum 126	ZfLib ZfAPI.SystemDir 117
ZfLib SendTimeEnum 127	ZfLib ZfAPI.UsersDir 117
ZfLib Server 99	ZfLib ZfAPI. Version 118
ZfLib Server.Check 100	ZfLib ZfAPI.ZetafaxServer 118
ZfLib Server.GetServerInfo 100	ZfLib ZfErr 129
ZfLib Server.Restart 100	ZfLib.Device.NumConnectFails 45
ZfLib Server.Start 101	ZfLib.Device.NumPages 45
ZfLib Server.Stop 101	ZfLib.Device.NumSendFails 46
ZfLib ServerInfo 101	ZfLib.Device.NumSendOK 46
ZfLib ServerInfo.Coversheets 102	ZfLib.Files.Add 50
ZfLib ServerInfo.Deferred 103	ZfLib.Link.NumReceived 58
ZfLib ServerInfo. Devices 103	ZfLib.Link.NumRejected 58
ZfLib ServerInfo.Letterheads 103	ZfLib.Link.NumTimedOut 59
ZfLib ServerInfo.Links 104	- D -
ZfLib ServerInfo.MaxDevices 104	- 0 -
ZfLib ServerInfo.MaxLinks 104	
ZfLib ServerInfo.RemoteAccept 105	Dynamic Data Exchange 227
ZfLib ServerInfo.RouterSub 105	Example DDE commands 229
ZfLib ServerInfo.Scanning 105	
ZfLib ServerInfo.Sending 106	- E -
ZfLib ServerInfo.WaitingConvert 106	
ZfLib ServerInfo.WaitingDevice 106	Embedded Addressing 231
ZfLib ServerInfo.WaitingResend 107	Attach 247
ZfLib StatusEnum 127	
ZfLib UserSession 107	Charge 248
ZfLib UserSession.APIPrint 108	Charge code 248
ZfLib UserSession.Coversheet 108	Commands 233, 234, 235, 236, 237, 238, 239, 240, 241, 242, 243, 244, 245, 246, 247, 248, 249
ZfLib UserSession.CreateNewMsg 109	240, 241, 242, 243, 244, 245, 246, 247, 248, 249, 250, 251, 252
ZfLib UserSession.FromName 109	Coversheet 241

Embedded Addressing 231 Delete 252 Discard 249 Fax 236 From 240 Header 246 Information 232 Letterhead 243 Mail Merge 253 Name 235 Note 251 Organisation 237 Preview 239 Priority 244 Quality 242 Send 238 Subject 250 Time 245 То 234

- F -

FAQ 21

- G -

Getting Started 10

Installing the API 11

- S -

Support 20

- Z -

ZSUBMIT 255 After 259 Append 284 Attach 260 285 Bold Charge 261 Comment 262 Coversheet 263 Covertext 264

Creating SUBMIT files 256 Date 286 Delete 265 Down 287 Fax 277 279 Field Field name 288 Font 289 Format 266 From 267 Header 268 Hold 269 290 Insert LAN User name 280 Landscape 291 292 Left margin 270 Letterhead Message option lines 258 Organisation 281 Page 293 Portrait 294 Preview 271, 300 Priority 272 Quality 273 Right 295 Send 299 SMS 278 Subject 274 Time 296 То 282 Underline 297 User name 275